

2022

# AJVoIP

## Android Java VoIP SDK

*The Mizu Android Java VoIP SDK (AJVoIP) is a compact SIP client library for Android compatible with all common VoIP devices, servers and softphones.*



Contents

About .....	3
Package content .....	3
Requirements.....	3
Usage .....	4
Instructions .....	4
Example code .....	6
Sample project .....	8
Features .....	8
Licensing .....	9
API.....	9
Functions.....	10
Notifications.....	24
Parameters .....	32
Basic Parameters .....	32
Advanced Parameters.....	33
FAQ .....	66
Resources .....	89

## About

The Android Java VoIP SDK (AJVoIP) is a SIP client library for the Android platform. Since it is based on the open standard [Session Initiation Protocol](#), it can inter-operate with any other SIP-based device (servers and clients).

[AJVoIP](#) is an easy to use compact Android SIP client library consisting of a single library file which have to be added to your project (one single aar or jar file) containing a simple high-level API (one single class).

With the Android SIP SDK you have a compact but full featured SIP/media stack, easy to integrate with any Android application. It can be used to develop a custom Android SIP client application or to add VoIP call capabilities into any existing Android application.

## Package content

The followings can be found in the [AJVoIP package](#):

- The library itself:
  - AJVoIP.aar (Android Archive file to be used with Android Studio)
  - AJVoIP.jar (jar file to be used with any other development environment such as Eclipse or Embarcadero Delphi / C++ Builder)
- Documentation:
  - SDK description: [software home-page](#)
  - Full documentation: [this document](#)
  - JavaDoc: [download](#)
- Sample project:
  - Test project (a working example) to be downloaded from [here](#)
- License:
  - AJVoIP comes with life-time license allowing commercial usage for your company (limited features and number of users with the Basic license, all features and unlimited users and calls with the Advanced and Gold license)
- Support:
  - Support is also included with your AJVoIP license for no extra cost. [Contact us](#) with any question/issue/bug report and we are here to help.
  - Upgrades: AJVoIP is actively maintained with at least one major new version per year including improvements, bug fixes and new features in each new release. Upgrades are always backward and forward compatible with no code changes required in your project.

## Requirements

- **Programming language:** Java, Kotlin, Scala or any other which can consume a aar/jar and can emit android apk such as Xamarin, Corona, Phonegap/Cordova, C++, Python, Groovy, Flutter, Xamarin, React, Ionic and others.
- **IDE:** For development you can use any environment which can produce android executables. The most popular options are Android Studio and Eclipse. You can use any operating system to work on your project: Windows, MAC, Linux.
- **SIP:** a SIP account at any VoIP service provider or your own IP-PBX/Softswitch/SIP sever. Can be also used without registration for peer to peer SIP calls.
- **Network:** All networks are supported with connection speed above 12 kbits including Wi-Fi and mobile GPRS, EDGE, 3G, 4G, LTE, 5G. VPN connections are also supported.
- **Size:** around 2 MB
- **RAM:** around 35 MB while in call. (This means that you can run the SIP engine also on low-end devices with 256 MB RAM or less)
- **CPU architecture:** any (Most of the library is pure Java. To improve performance, some audio processing and codec related functionalities are implemented as native ABI modules for all the popular platforms (arm, x86 and mips, including 64bit versions)
- **CPU speed:** any (The library will auto detect the CPU performance and it might disable some features on old/slow CPU's, such as G.729, wideband and AEC which means that you can run it even on low-end 100 MHz ARM processors)
- **API level:** All Android API/SDK versions are supported (AJVoIP is optimized to old API levels but also takes full advantage of the features found in latest versions if you are running it on a compatible OS)
  - Minimum (minSdkVersion): 14 (released in 2011 with Android 4.0 Ice Cream Sandwich), which means compatibility also with ancient phones covering 100% of the market.  
*Note: On request, we can ship also build with minSdkVersion 9 (this might be necessary only if you wish to target some specific/outdated hardware such as old TV or media player)*
  - Target (targetSdkVersion): 14 or higher (you should set this as high as possible for your project environment)  
*Note: due to Google Play [regulations](#) you must target minimum API 26 beginning from 2018. Using API level below 26 can be useful only if you don't plan to distribute your app via Google Play.*
  - Compile: The compileSdkVersion must be set to 23 or higher, preferably 28 or higher (you should set it to highest possible by your project environment)
  - Maximum: 33+. API level 33 introduced with Android 13 in 2022. The SDK is continuously tested and optimized to latest API levels as released by Google while also keeping full backward compatibility with old API levels. You can expect to work it also in all future versions with no modifications required and we also add optimizations to latest API levels when new versions are released if there is any new Android feature that can be exploited by the VoIP SDK.
- **Required permissions:**  
You can set these in your AndroidManifest.xml as [uses-permission](#) elements:
  - Dangerous/Mandatory (your app must have permission for this):
    - RECORD\_AUDIO (used for the audio input stream)
  - Dangerous/Optional (permission have to be asked only if some features are needed):

- READ\_PHONE\_STATE (used only if the rejectonphonebusy parameter is set to 0 or 2)
- READ\_EXTERNAL\_STORAGE (used only for call recording and only if you wish to store files to external storage)
- WRITE\_EXTERNAL\_STORAGE (used only for call recording and only if you wish to store files to external storage)
- CAMERA (used only if you need video calls)
- READ\_CONTACTS and WRITE\_CONTACTS (not required for AJVoIP at all, but might be needed for your app if you wish to manage contacts)
- Normal (permissions are granted automatically for these, just add them into your manifest.xml):
  - INTERNET (mandatory)
  - ACCESS\_NETWORK\_STATE (optional but highly recommended)
  - CHANGE\_NETWORK\_STATE (optional)
  - ACCESS\_WIFI\_STATE (optional)
  - CHANGE\_WIFI\_STATE (optional)
  - BLUETOOTH (optional)
  - DISABLE\_KEYGUARD (optional)
  - VIBRATE (optional)
  - FOREGROUND\_SERVICE (optional since API level 27 if you wish to launch the sipstack from a foreground service)
  - REQUEST\_IGNORE\_BATTERY\_OPTIMIZATIONS (optional for API level 26 or above running the sipstack as a service)
  - WAKE\_LOCK (optional but highly recommended)
  - RECEIVE\_BOOT\_COMPLETED (needed only if you wish to run it as a service and auto-start)

*Note: there is no need to ask for permissions at runtime if your application target API level 22 or below, however API level 26 is mandatory in Google Play since 2018. More details about permissions can be found [here](#).*

- **Required android features:**

You can set these in your AndroidManifest.xml as [uses-feature](#) elements:

The only important feature is the android.hardware.microphone (but this is also not enforced by default by the library because you might use it for other purposes when no media recording is required for calls).

For a usual SIP client application you should add the following line to your manifest:

```
<uses-feature android:name="android.hardware.microphone" android:required="true" />
```

The RECORD\_AUDIO permission must be also asked at runtime as described [here](#). AJVoIP will ask for this on first audio device opening, but it is better if you ask it also from your app at a more appropriate time (for example at startup or before the first call).

Other features that might be used by the library (thus might be required by your application) are the followings:

- android.hardware.audio.low\_latency
- android.hardware.audio.output
- android.hardware.audio.pro
- android.hardware.telephony
- android.hardware.bluetooth
- android.hardware.wifi
- android.hardware.sensor.proximity
- android.hardware.camera
- android.software.sip
- android.software.sip.voip
- android.software.webview

None of these are crucial so you might add them to your manifest with required set to false or don't add at all if not mandatory for your use-case.

## Usage

You can use the AJVoIP library in any Android project. Just add the library to your project and call its public API [functions](#).

## Instructions

Step-by-step instruction for using AJVoIP:

1. Download AJVoIP from [here](#) (this is the demo version) or from the link provided by Mizutech (paid versions) and unzip. You might load the [sample project](#) first and check its [MainActivity.java](#) file for a simple but working usage example.
2. Add the SIP library to your project
 

You can use either the AJVoIP.aar file or the AJVoIP.jar file. If you are using Android Studio then we recommend the aar file. Otherwise the jar file.

  - For Android Studio you can add it to your project this way:
    - 1) Click File > New > New Module.
    - 2) Click Import .JAR/.AAR Package then click Next.
    - 3) Enter the location of the AJVoIP.aar file then click Finish.
    - 4) Make sure the library is listed at the top of your settings.gradle file:
 

```
include ':app', ':AJVoIP'
```
    - 5) Open the app module's build.gradle file and add a new line to the dependencies block:
 

```
dependencies {
    ...
    implementation project(":AJVoIP")
}
```
    - 6) Click Sync Project with Gradle Files.

7) More details can be found [here](#)

- If you are using Eclipse then follow these steps:

- 1) Create a folder called libs in your project's root folder
- 2) Copy the AJVoIP.jar file to the libs folder
- 3) Now right click on the AJVoIP.jar file and then select Build Path > Add to Build Path, which will create a folder called 'Referenced Libraries' within your project
- 4) You can read more details [here](#)

- If you are using other IDE or environment:

Just import the AJVoIP.jar into your project and use its public class.

### 3. Instantiate a SipStack object

Add the following code to the location from where do you wish to start the SIP client:

```
import com.mizuvoip.jvoip.SipStack; //import the SipStack class from AJVoIP
SipStack mysipclient = null; //declare the SIP stack object variable somewhere in your application
mysipclient = new SipStack(); //create the SIP Stack instance.
mysipclient.Init(context); //initialize the SIP stack
//The context parameter is your application Context which can be obtained from any activity or as described here
```

### 4. Call the SetParameter (or the SetParameters) function to pass any settings

```
mysipclient.SetParameter("loglevel","5"); //set loglevel
mysipclient.SetParameter("serveraddress","voip.mizu-voip.com"); //set your voip server domain or IP:port
mysipclient.SetParameter("username","sdktest2"); //set SIP username
mysipclient.SetParameter("password","sdktest2"); //set SIP password
//you might set other parameters here such as proxyaddress, autoaccept and many others. See the parameters chapter for the full list of possible parameters.
```

### 5. Call the Start() to start the sipstack

```
mysipclient.Start(); //this will start the SIP stack internal main thread. It might also auto register, depending on the "register" parameter
//mysipclient.Register(); //if you have set the "register" parameter to 0, then you might need to register explicitly
```

### 6. Call any of the API [functions](#). This is where the actual work is done. Example:

```
mysipclient.Call(-1, "testivr3"); //init call to "testivr3". Possibly behind a "Call" button.
mysipclient.SendChat(-1, "john", "hi"); //send "hi" text message to the john SIP user or SIP extension. Possibly behind a "Chat" button.
```

Use any other [API](#) (for example to send DTMF, set presence, call transfer, conference or other functions)

### 7. Parse and process the notifications from the sip stack after your needs. This can be done continuously polling the [GetNotifications](#) in a separate thread and parsing of the returned messages as described in the [notifications](#) chapter:

```
public void run()
{
    while(!terminated)
    {
        String notification = mysipclient.GetNotificationsSync();
        if(notification.length() > 0)
        {
            //parse the strings and handle the events after your needs
        }
    }
}
```

Adjust your state machine and GUI according the notifications received (the [STATUS](#) notification is the most relevant)

### 8. Fine-tune your application by adjusting any additional [parameters](#) that might be needed for your use-case.

Scroll trough the [FAQ](#) to find the answer for the most relevant issues and potential features such as [native call integration](#) or [call transfer](#) usage. [Contact us](#) if you run into any issue or with any question

## Project configuration

There are no any specific requirements regarding your Android project, IDE or environment. You just need to add the AJVoIP.aar into your Android Studio project (or the AJVoIP.jar if you are using some other IDE) and you are ready to go by importing the API class (`import com.mizuvoip.jvoip.SipStack;`)

The followings are to be considered for your gradle and manifest file.

The basic requirements are the followings (SDK / api level settings for your app):

- Set the `minSdkVersion` to 14 or higher (the minimal SDK version your app is prepared to handle. Let us know if for some reason you need to go below 14)
- Set the `compileSdkVersion` to 23 or higher, preferably 29 or higher (depending on the SDK version you wish to use to compile your project; you should set this to as high as possible)
- Set the `targetSdkVersion` to at least to the minimum API level allowed in Google Play when your publish your app, 31 or higher in 2022 (It is recommended to set this to a value to cover most of the phones on the [market](#) and Google Play doesn't allow targeting too old API levels)

The AJVoIP library itself have been built with the following SDK/API settings:

- min SDK: 14 (this gives you a lot of flexibility, allowing your app to target any SDK versions you wish starting with the already ancient v.14)
- target SDK: 29
- compile SDK: 29

- the library might load API level 14+ (including v.29) features at run-time with class-loader or support libraries when it is running on a new devices, taking full advantage of the latest Android platform features.

If your minSdkVersion is 20 or below (prior to Android 5.0), then you should enable multidex as described [here](#).

The library depends also on android support library (this is to allow your project to compile and target any SDK using any API level since 14).

You might need to add it into your gradle config as well:

```
dependencies {  
    ...  
    implementation 'androidx.legacy:legacy-support-v4:1.0.0'  
}
```

The only “dangerous” permission required by default is audio recording. For this you should add the following lines to your AndroidManifest.xml:

```
<uses-permission android:name="android.permission.RECORD_AUDIO"></uses-permission>  
<uses-feature android:name="android.hardware.microphone" android:required="true" />
```

Above API level 23 the permission request should be handled at runtime as described [here](#) and [here](#).

Permissions can be requested from your own code, however the AJVoIP will also check (and ask for permission if needed) for RECORD\_AUDIO (for calls) and CAMERA (on video calls).

You must also add the following non-dangerous permissions to your AndroidManifest.xml (allowed automatically, no need for explicit permission request):

```
<uses-permission android:name="android.permission.INTERNET"/>
```

All other permissions and features are optional and handled gratefully by the library if not granted. For a full list see the “Required Permissions” section [here](#).

You need to take care of these only if your app requires a specific feature depending on one of these permissions.

More details about permissions can be found [here](#).

For a basic gradle config file, see the build.gradle file in the [sample application](#) (inside the “app” subfolder).

You might also check the [gradle file](#) of our [MizuDroid](#) softphone (this is a full featured SIP softphone based on the AJVoIP library with a long list of features).

For a basic manifest file, see the AndroidManifest.xml in the [sample application](#).

You might also check the [manifest file](#) of our MizuDroid softphone used in production.

You should be able to use any [proguard](#) rules for your project as this will not affect the AJVoIP usage (the SIP library itself is already highly optimized, but with its interface class kept untouched).

You might need to slightly modify your project config to match your requirements, however in overall AJVoIP doesn’t impose any hard limitations on the required configurations and you should be able to use the library in any environment with any settings if you respect the minimal requirements (min/target/compile SDK versions as described above).

## Example code

//error handling removed for simplicity

-----  
File: YourCodeSipCall.java  
-----

```
package yourpackagename;  
import com.mizuvoip.jvoip.SipStack; //import AJVoIP
```

```
//create SipStack class object instance:  
SipStack mysipclient = new SipStack();
```

```
//start your message listener to accept the notifications from the SIP engine:  
SIPNotifications sipnotifications = new SIPNotifications(mysipclient);  
sipnotifications.Start();
```

```
//initialize the SDK:  
mysipclient.Init((Context)this);
```

```
//set parameters (replace uppercase words):  
mysipclient.SetParameter("serveraddress", "VOIP_SERVER_IP_OR_DOMAIN");  
mysipclient.SetParameter("username", "SIP_USERNAME");  
mysipclient.SetParameter("password", "SIP_PASSWORD");  
mysipclient.SetParameter("loglevel", "5");  
//you might set other parameters here
```

```
//start the sipstack:  
mysipclient.Start();
```

```
//register to your SIP server if needed (usually not needed since the above Start can also auto-register, depending on the "register" parameter):
mysipclient.Register();

//make a call to a user/extension/phone number/SIP URI (note: 1-2 seconds might be needed between Start/Register and Call for the sipstack to initialize)
mysipclient.Call(-1, "DESTINATION");
//the following lines should be used from another function
//during the call you might call call divert functions by your app logic or on user interaction, for example Hold()

//call hangup to end the call (possibly triggered by a "Hangup" button pressed by the user):
mysipclient.Hangup(-1);
//stop AJVoIP when you don't need it anymore
mysipclient.Unregister();
sipnotifications.Stop();
```

---

File: SIPNotifications.java

---

```
package yourpackagename;
import com.mizuvoip.jvoip.SipStack; //import AJVoIP

public class SIPNotifications extends Thread
{
    boolean terminated = false; //thread state
    SipStack mysipclient = null;
    //ctor
    public SIPNotifications(SipStack mysipclient_in)
    {
        mysipclient = mysipclient_in;
    }

    //start thread
    public boolean Start()
    {
        try{
            this.start();
            return true;
        }
        catch (Exception e)
        {
            e.printStackTrace();
        }
        return false;
    }

    //use this function from external code when the sipstack is not needed anymore (when you app is closing).
    public void Stop()
    {
        terminated = true;
    }

    public void run()
    {
        try{
            //variable to hold the incoming messages
            String notifications;

            //continuous blocking read until thread is terminated:
            while (!terminated) {
                notifications = mysipclient.GetNotificationsSync(); //get the notifications from the SIP stack
                if(notifications.length() > 0)
                {
                    ProcessNotifications(notifications);
                }
            }
        }
        catch (Exception e)
        {
            if(!terminated) e.printStackTrace();
        }
    }

    //parse sdk messages and modify your state (user interface, program logic) accordingly. This might not be necessary for simple basic usage.
    public void ProcessNotifications(String msg)
```

```

{
    System.out.println("received from ajvoip: " + msg+"\r\n");
    //process notifications here (change your user interface or business logic depending on the sipstack state / call state).
    //see the Notifications section in the documentation for the details. Example code can be found here.
}
}

```

See the [API](#) and the [parameters](#) sections below for the details about the usage.

## Sample project

You can download a working example from [here](#).

Usage:

1. [Download](#) and unzip the AJVoIPTest.zip file
2. Open the project in Android Studio
3. Copy the **AJVoIP.aar** into the `\AJVoIPTest\AJVoIP` folder! (from [the demo](#) or from the package sent to you by Mizutech)
4. You might also need to adjust the SDK version and location in the following files:  
`local.properties`  
`\app\ build.gradle`
5. From Android Studio select **Rebuild Project** from the Build menu. Once the rebuild is ready, you can **Run** it (on your device or in emulator)

The relevant code can be found in the `\AJVoIPTest\app\src\main\java\com\ajvoiptest\MainActivity.java` [file](#).

This is an Android Studio example project. If you are using Eclipse or other environment, then just inspect the above file or convert the project to your environment.

For a full demonstration of the SDK capabilities you might check the [MizuDroid Android softphone](#) which is also based on this SDK.

## Features

AJVoIP is a full featured SIP library for Android with all the usual telephony features implemented and many other extra features.

- Standard SIP client for calls (in/out), chat, conference and others
- **SIP** and RTP stack compatible with any VoIP server or client (Cisco, Asterisk, gateways, ATA, softphones, IP Phones, X-Lite and many others)
- Compatible with all Android devices (phones, tablets, TV's and others). SDK compatibility with 100% of the market share (min SDK: 9) and always optimized for latest Android versions while keeping full backward compatibility even with ancient devices
- Protocols: SIP/SIPS, RTP/SRTP. Transport: UDP, TCP, TLS, TCP tunnel, SOCKS proxy traversal, HTTP proxy traversal, HTTP, VPN tunneling
- NAT/Firewall support: stable SIP and RTP ports ,keep-alive, UPnP, rport support, fast ICE/fast STUN protocols and auto configuration
- Encryption: **TLS/SRTP**, tunneling and peer to peer encrypted media (if direct routing is not disable by your SIP server SDP negotiation)
- RFC's: 2543, 3261, 2976, 3892, 2778, 2779, 3428, 3265, 3515, 3311, 3911, 3581, 3842, 1889, 2327, 3550, 3960, 4028, 3824, 3966, 2663, 3022 and others
- Supported methods: REGISTER, INVITE, reINVITE, ACK, PRACK, BYE, CANCEL, UPDATE, MESSAGE, INFO, OPTIONS, SUBSCRIBE, NOTIFY, REFER
- Audio codec: PCMU, PCMA, **G.729**, GSM, iLBC, SPEEX, **OPUS**
- RTC Video codec: H264, VP8, VP9
- HD Audio: Wideband, **ultra-wideband** and full-band codecs (speex, opus)
- Audio enhancements: PLC (packet loss concealment), **AEC** (acoustic echo canceller), Noise suppression, Silence suppression, AGC (automatic gain control), VAD (voice activity detection), audio focus and auto QoS (quality of service)
- **Conference** calls (built-in RTP mixer)
- **Voice recording** (SIPREC, local, FTP or HTTP upload in wav, gsm or ogg format), custom audio streaming
- DTMF (SIP INFO method in signaling, RFC 2833, In-Band)
- **IM/Chat** (RFC 3428), offline chat support (caching messages when peer is not online), group chat
- IMS/3GPP (basic compatibility and features such as USSD and 3GPP SMS)
- **BLF** (busy lamp field)
- **Presence** capability
- Redial, call **hold**, mute, **forward** and **transfer** (attended and unattended)
- Call park and pickup, barge-in
- Additional call features: call fork, re-INVITE, 3PCC, ED-137, early media, local ring-back, PRACK and 100rel, replaces
- Balance display, call timer, inbound/outbound calls, Caller-ID display, **voicemail** (MWI)
- Support for credit (balance) and call rating display
- Custom ringtone
- Contact management
- **Native call integration** support (including the new ConnectionService support)
- Auto handle phone power state, idle state, charging and airplane mode
- Call optimizations such as proximity sensor, WiFi lock/reconnect and optimal wake-looks (CPU/keyboard/screen)



- Unlimited lines, multiple accounts
- Support for run as service with minimal battery usage (including bypassing background service limitations)
- Support for **push notifications**
- AdMob, auto-provisioning, QR code provisioning (for custom builds)
- A long list of other features (see the parameter list and the API for the details)
- Flexibility (all parameters/behavior can be changed/controlled by settings and/or the API)
- **Auto adapt** to hardware: auto turn on/off features based on CPU type and RAM size, so it will run also on low-end hardware
- **Reliable incoming calls** with all-time availability using improved service mode and/or push to handle situations where your device or app is closed, **standby** or the device is in **doze** or **sleeping** state
- Auto adapt to networking circumstances: different codec parameters and prioritization based on network type (WiFi/3G/LTE/others) and quality (bandwidth/packet loss/jitter)
- Stable high-level API: Always backward and forward compatible including the parameters and the API (you don't need to change your code when upgrading to new versions)

## Licensing

The Mizu Android Java VoIP SDK (AJVoIP) is sold with life-time unlimited client license (Advanced and Gold) or restricted number of licenses (Basic and Standard). You can use it with any VoIP server(s) which belongs to you or your company. Your VoIP server(s) address (IP or domain name) will be hardcoded into the software to protect the licensing. You can find the licensing possibilities on the [Android SIP SDK](#) page. After successful tests please ask for your final version at [info@mizu-voip.com](mailto:info@mizu-voip.com). Mizutech will deliver the AJVoIP build (your licensed copy) within one workday on your payment.

Release versions don't have any of the demo limitations and can be fully customized with your branding with "mizu", "mizutech" words, links and all reference to Mizutech removed. Your final build must be used only for you company needs (including your direct sip endusers and VoIP clients).

The library doesn't have any external dependencies (everything it requires is within the .aar / .jar file).

Title, ownership rights, and intellectual property rights in the Software shall remain with MizuTech and/or its suppliers.

The agreement and the license granted hereunder will terminate automatically if you fail to comply with the limitations described herein. Upon termination, you must destroy all copies of the Software. The software is provided "as is" without any warranty of any kind.

You may:

- Use AJVoIP on any number of devices or as permitted by your license
- Use AJVoIP as an SDK embedded in your Android project
- Use AJVoIP with VoIP servers for which you have license for (after the agreement with Mizutech). All the VoIP servers must be owned by you or your company. Otherwise please contact our support to check the possibilities (the Gold license allows 10+ or freely configured SIP server address)

You may not:

- Resell AJVoIP
- Use AJVoIP with VoIP servers not communicated with Mizutech, except Gold license
- Reverse engineer, decompile, disassemble or modify the software in any way (except modifying the parameters and using it via the public API)

## Demo version:

We are providing a demo version which you can try and test before any payment. The demo version has all features enabled but with some restrictions to prevent commercial usage. The limitations are the followings:

- maximum 10 simultaneous AJVoIP instances in the same time
- will expire after several months of usage (usually 2 or 3 months)
- maximum ~100 sec call duration restriction
- maximum 10 calls / session limitation (after 10 calls you will have to restart)
- will work only maximum 20 minutes and after that you have to restart the AJVoIP library or your application
- verifications against the mizu license service

Note: for the first few calls there might be fewer limitations than described above.

On your [request](#) we can also send a trial version (will expire after some time but doesn't have the above demo limitations).

## API

You can use AJVoIP as an SDK by embedding into your Android application and calling its public API functions described below.

The whole API is defined in the SipStack class, thus you will need to import only this single class once you added AJVoIP.aar or AJVoIP.jar to your project:

```
import com.mizuvoip.jvoip.SipStack;
```

For maximum flexibility, the Android SIP SDK exposes numerous functions, however this doesn't mean that the usage is difficult. You can ignore most of them and use only those few relevant for your needs also outlined in the usage [example](#).

For example if you just need to make simple calls, then the following five functions will cover all your needs: Init, SetParameters, Start, Call, Hangup.

## General considerations

All API calls are **thread safe** and will **not throw exceptions** (on exception or error they will send "ERROR" notifications and/or return false/-1 depending on the context).

API calls never returns null (in case of strings you will always receive an empty string return value when needed instead of null).

Most of the functions **return a boolean** value. True when the operation was completed or initiated successfully, otherwise false.

Most of the functions are executed **asynchronously** (non-blocking) such as the Call and Register. This means that it can return a true value immediately and fail later. For example for the Call function the return value means only that the call was initiated successfully. At this point we don't know if the call will be successful (connected) or not (rejected or failed). You can get the call status by parsing the notification messages or you can periodically poll AJVoIP status with the GetStatus function.

The **line** parameter is part of most of the functions and it means the channel number to be used if you wish to select a specific session.

For simple use cases usually you just have to set it to **-1**. For the details, see the "[Line parameter](#)" and the "[Multiple lines](#)" FAQ points.

## Functions

The list of public functions exported by the SipStack class are described below:

### SipStack()

Constructor. Create new SIP stack instance by creating a new SipStack object:

```
SipStack mysipclient = new SipStack();
```

### boolean Init(Context context\_in)

Initialize the SIP engine. This is the very first function you must call to initialize the internal data structures.

The context\_in parameter is your application [Context](#) which can be obtained from any activity or as described [here](#).

### boolean SetParameter(String param, String value)

Configure the Android SIP library by passing any settings.

The full list of available parameters are listed [here](#).

Example: `wobj.API_SetParameter("loglevel", 5);`

Notes:

Some basic parameters should be set before the Start function have been called (such as "register"), however most parameters can be also changed at run-time.

Some advanced parameters can be set also by line using the [SetLineParameter](#) function (for advanced users only; use the other API functions instead to control the [individual lines](#)).

### boolean SetParameters(String parameters)

You can pass a set of parameters with this function in value=key lines separated by CRLF (\r\n).

It has the same effect like the above SetParameter function, but uses a list of parameters at once instead of setting them individually.

See the full list of supported parameters [here](#).

Example: `mysipclient.SetParameters("loglevel=5\r\ndtmfmode=1\r\n");`

### boolean SetCredentials(String server, String username, String password, String authname, String displayname)

Will set the SIP server address (ip:port or domain:port) the SIP username and the password. These values can also be preset by parameters.

Parameters with empty strings will be omitted. For example if you would like to change only the username and the password, you can write `SetCredentials("", "newusername", "newpassword")`

If authname is empty, then the username will be used for authentications. The displayname is usually empty (no special displayname will be presented for peers). If other parameters are empty, then they can be specified by user input (If the Android SIP SDK has a visible user interface).

Note: you can also use the SetParameter(s) to initialize the SDK with the credentials.

### ***boolean SetCredentialsMD5(String server, String username, String md5, String realm)***

Instead of passing the password directly you can use MD5 checksum.

In this case the md5 parameter must be the md5 checksum for username:realm:password

The realm parameter is optional (can be set as an empty string) but it is recommended for easy error detection. If present and the server realm don't match with this one, an error message will be displayed by AJVoIP.

### ***boolean Start()***

Will start the SIP engine (starting the internal main thread).

### ***boolean StartStack()***

This function call is optional to start the sip stack on demand.

If not called, then the sip stack is started anyway if the "startsipstack" parameter is set, otherwise will start at first registration or outgoing call attempt.

### ***boolean Register()***

Will connect to the SIP server. This can be also done automatically by parameter ("register"). This function have to be called only once at the startup. Further re-registrations are done automatically based on the "registerinterval" parameter. When called subsequently, the old registrar endpoint is deleted, a new one will be created with a new call-id and AJVoIP will reregister.

Even if you wish to force re-registration, you should not call this more frequently than 40 seconds (because up to 40 seconds might be needed for a slow registration attempt)

### ***boolean Register(String server, String username, String password, String authname, String displayname)***

Same as the above but with parameters. Otherwise you can set the credentials with the SetParameter(s) function before to call Register().

### ***boolean RegisterEx(String accounts)***

You can use this function to register multiple secondary accounts (up to 99) on the same or other servers.

The accounts parameter must have the following format: server,usr,pwd,...;server2,usr2,pwd2,...;

See the [Multiple account registration](#) FAQ for more details.

### ***boolean Unregister()***

Will stop all endpoints (hangup current calls if any and unregister)

### ***boolean CheckVoicemail(int line)***

Will (re)subscribe for voicemail notifications. No need to call this function if the "voicemail" parameter is set to 2.

The line parameter should be set to -1.

### ***boolean SetLine(int line)***

Will set the current channel. (Use only if you present line selection for the users. Otherwise you don't have to take care about the lines).

Note: Instead of using each API call with the line parameter, you can just use this function when you wish to change the active line and use all the other API calls with -1 for the line parameter.

### ***int GetLine()***

Will return the current active line. This should be the line which you have set previously except after incoming and outgoing calls (the SIP client will automatically switch the active line to a new free line for these if the current active line is already occupied by a call)

### ***int GetLineStatus(int line) or string GetLineStatusText(int line)***

Query the status of the line.

*Note: this is rarely needed since you receive the status also by event notifications*

### ***String GetLineDetails(int line)***

Get details about a line. The line parameter can be -1 (will return the "best" line status).

Will return the following string:

LINEDETAILS,line,state,callid,remoteusername,localusername,type,localaddress,serveraddress,mute,hold,remotefullname

**Line** line number (might be useful if you pass -1 as line parameter)

**State** same as in STATUS notification

**CallID:** SIP session id (SIP call-id)

**Remoteusername** is the other party username (if any)

**Localusername** is the local user name (or username).

**Type** is 1 from client endpoints and 2 from server endpoints.

**Localaddress:** local IP:port

**Serveraddress:** remote IP:port

**Mute:** is muted status. 0=no,1=undefined,2=hold,3=other party hold,4=both in hold (or if you wish to simplify: 0 means no, others means yes)

**Hold:** is on hold status: 0=no,1= undefined,2=hold,3=other party hold,4=both in hold (or if you wish to simplify: 0 means no, others means yes)

**Remotefullname** is the other party display name if any

### ***boolean Call(int line, String peer)***

Initiate call to a number or sip username.

If the peer parameter is empty, then will redial the last number.

- *Example:*
  - `mysipclient.Call(-1, "004401234567");` //call to phone number on the default line
  - `mysipclient.Call(2, "bob");` //call to sip username on the second line
- *It is recommended to pass only the peer number, extension or username to this function and not the full SIP URI (the SIP stack will construct the full SIP URI with the serveraddress already set)*
- *This function is for normal audio calls. For video use the [VideoCall](#) API.*

### ***boolean Hangup(int line, String reasontext)***

Disconnect current call(s). If you set -2 for the line parameter, then all calls will be disconnected (in case if there are multiple calls in progress). The "reasontext" parameter is optional.

### ***boolean Accept(int line)***

Connect incoming call.

### ***boolean Reject(int line)***

Disconnect incoming call. (Hangup will also work)

### ***boolean Ignore(int line)***

Ignore incoming call.

### ***boolean Forward(int line, String peer)***

Forward incoming call to peer (with 302 Moved Temporarily disconnect code)

### ***boolean Transfer(int line, String peer)***

Transfer current call to peer which is usually a phone number or a SIP username. (Will use the REFER method after SIP standards).

You can set the mode of the transfer with the "transfertype" parameter.

If the peer parameter is empty than will interconnect the currently running calls (should be used only if you have 2 simultaneous calls)

### ***boolean SetSpeakerMode(boolean loud)***

Switch between speakerphone and loudspeaker.

Set to loud parameter true if you wish to set to speaker/loudspeaker. Otherwise false for normal earspeaker/earpiece.

### ***boolean Mute(int line, boolean mute, int direction)***

Mute current call.

The line parameter is the endpoint. -2 for all or -1 for current line.

Set the mute parameter to true for mute or false to un-mute.

The direction can have the following values:

- 0: mute in and out
- 1: mute out (speakers)
- 2: mute in (microphone)
- 3: mute in and out (same as 0)
- 4: mute default (set by the “defmute” parameter, which is “mute microphone only” by default)

### ***int IsMuted(int line)***

Return if the selected line is muted or not.

Return values:

- -1: unknown
- 0: not muted
- 1: both muted (in/out)
- 2: out muted (speaker)
- 3: in muted (microphone)
- 4: both muted (in/out; same as 1)

### ***boolean Hold(int line, boolean hold)***

Hold current call. This will issue an UPDATE or a reINVITE.

Set the second parameter to true for hold and false to reload.

### ***int IsOnHold(int line)***

Query if the selected line is on hold or not

Return values:

- -1: unknown
- 0: no
- 1: not used
- 2: on hold
- 3: other party held
- 4: both in hold

*Note: pass -2 for the line to find if any endpoint is in hold*

### ***boolean Conf(String peer)***

Add people to conference.

If peer is empty than will mix the currently running calls (if there is more than one call)

Otherwise it will call the new peer (usually a phone number or a SIP user name) and once connected will join with the current session.

### ***boolean ConfEx(int line, String peer, boolean add)***

Add/remove people or line to conference.

If peer is empty than:

-if add is true:

-if line is -2 then it will mix all the currently running calls (if there is more than one call)

-if line is not -2, then it will add the channel to the conference

-if add is false:

-if line is -2 then it will destroy the conference (but will keep the calls on individual lines)

-if line is not -2 then it will remove the selected line from the conference

Otherwise it will call the new peer (usually a phone number or a SIP user name) and once connected will join with the current session.

### ***boolean Dtmf(int line, String dtmf)***

Send DTMF message by SIP INFO, In-Band or RFC2833 method (depending on the “[dtmfmode](#)” parameter). Please note that the dtmf parameter is a string. This means that multiple dtmf characters can be passed at once and the Android SIP library will streamline them properly. Use the space char to insert delays between the digits. The dtmf messages are sent with the protocol specified with the “dtmfmode” parameter.

Example: `Dtmf(-2, “12 345 #”);`

*Note: dtmf messages can be also sent by adding it to the called number after a comma. For example if you make a call to 123,456 then it will call 123 and then it will send dtmf 456 once the call is connected.*

### ***boolean Info(int line, String msg)***

Send any SIP INFO message as defined in [RFC 2976](#).

Use this API to send any custom INFO messages to the server or to the connected peer (in case if your server will forward it to other peer and not discard it).

The msg string will be sent in the INFO body.

The Content-Type can be specified with the **infocontenttype** parameter. For example you might set the **infocontenttype** to "application/mydata". If the **infocontenttype** is not set then it will be auto guessed as application/json, application/xml or application/octet-stream"

Feedback about the message delivery can be received with the [INFO](#) notifications.

Example: `API_Info(-2,"MyMessage");`

For more details see the [Custom INFO messages](#) FAQ point.

### ***boolean SendUSSD(int line, String method, String ussd)***

Send an USSD message after the IMS [3GPP TS 24.390](#) standard.

The method parameter can be set to "INVITE", "INFO" or "BYE".

If INVITE, then a new session will be created. Otherwise will use the session suggested by the line parameter.

The ussd parameter have to be set to the USSD string (for example "\*135#" ) or whole XML ("<?xml version ... ").

Will return true if send initialized successfully or false on failure.

Further feedback about the actual delivery or incoming ussd messages can be obtained from the [USSD](#) notifications.

More details [here](#).

### ***boolean SendChat(int line, String peer, String message)***

Send a chat message. (SIP MESSAGE method after RFC 3428)

Peer can be a phone number or SIP username/extension number.

Parse the CHAT notification to check if delivery succeeded or failed.

On successful delivery you will also receive a log like: EVENT, chat sent successfully

On failed delivery you will also receive a log like: WARNING, chat message not delivered

You can also send typing notifications with the SendChatIsComposing API.

### ***boolean SendSMS(int line, String peer, String message)***

Send a SMS message if softswitch has SMS delivery capabilities (Otherwise might try to deliver as IM).

The message is delivered as a 3GPP SMS, SMS HTTP API request or a standard SIP MESSAGE with X-Sms: Yes header (in this case the server is responsible to convert it to SMS).

Note: incoming SMS messages are reported as [CHAT notifications](#).

### ***boolean VideoCall(String destination, int fragmentResId, FragmentActivity fragmentinstance)***

Initiate RTC video call to destinationnumber which can be a number, username or SIP URI.

The fragmentResId is the Integer resource ID of the FrameLayout in which the video fragment will be loaded.

The fragmentinstance is the instance of the Activity in which the video module will be displayed. The video module consists of an android [Fragment](#) and the FragmentActivity will be its parent.

Place the <FrameLayout> in your Activity's content XML.

```
<FrameLayout xmlns:android="http://schemas.android.com/apk/res/android"
    android:id="@+id/fragment_container"
    android:layout_width="fill_parent"
    android:layout_height="350dp" />
```

In the above example the resource ID will be: `R.id.fragment_container`

RTC capabilities must be available for the video to work.

### ***boolean AcceptVideo(int fragmentResId, FragmentActivity fragmentinstance)***

Accept RTC video call.

The fragmentResId and fragmentinstance is as described at the VideoCall API above.

If video interface is not loaded yet, then will initiate it now and call back. If incoming call is not with video, then it might result in simple audio call.

### ***boolean RemoveVideo()***

Will remove the video fragment (will also disconnect pending video call if any).

*Instead of this function, you should just hide/destroy your video container element from the user interface.*

*More details can be found [here](#).*

### ***boolean SetVideoDisplaySize(int type, int width, int height)***

Use this function to control the video display size (both for remote and local video).

Accepted parameters:

- type: 1=for remote video container, 2=for local video container
- width: width in pixels
- height: height in pixels; this parameter can be 0, and the height will be set depending on the video's aspect ratio

### ***boolean VoiceRecord(int startstop, int now, String filename)***

Will start/stop a voice recording session.

- Startstop: 0 to stop, 1 to start locally, 2 to start remote ftp, 3 start to record both locally and to remote ftp, 4 start to record as it is set by the "voicerecording" parameter
- Now: used if the startstop is set to 0. 0 means that the recorded file will be saved and/or uploaded at the end of the conversation only. 2 means that the file will be saved immediately
- Filename: file name used for storing the recorded voice (if empty string, then will use a default file name)

*This function should be used only if you would like to control the recording duration.*

*If all conversations have to be recorded, then just set the "[voicerecording](#)" parameter after your needs.*

*The last recorded call can be played by calling the PlaySound with the file set to "lastvoicerecord".*

### ***boolean PlaySound(int start, String file, boolean islocal, boolean toremotepeer, int line)***

Play any sound file.

At least wave files are supported in the following format: PCM SIGNED 8000.0 Hz (8 kHz) 16 bit mono (2 bytes/frame) in little-endian (128 kbits).

This function can be used to play audio locally, but also for remote streaming.

For remote playback, make sure to force a narrowband codec if your file is narrowband and wideband codec (speex, opus) if your file is wideband (16 kHz, 16 bit mono in little-endian).

The file must be found locally.

- start: 1 for start or 0 to stop the playback, -1 to pre-cache
- file: file name
- islocal: true if the file have to be read from the device file system. False if remote file (for example if the file is on the webserver)
- toremotepeer: stream the playback to the connected peer
- line: used with toremotepeer if there are multiple calls in progress to specify the call (usually set to -1 for the current call if any)

*For remote playback you can pass any file path which can be passed for FileInputStream as our code uses FileInputStream to load the file like this:*

*`FileInputStream fileinputstream = new FileInputStream(file);`*

Examples:

*-playback a file locally (mysound.wav must):*

*`PlaySound(1, "mysound.wav", false, false, -1)`*

*-playback a file to the connected remote peer (mysound.wav must exist):*

*`PlaySound(1, "mysound.wav", false, true, -1)`*

*-stop the playback:*

*`PlaySound(0, "", false, false, -1)`*

*In case if you just want to play a file locally, then you can do it also directly from your code like this:*

*`MediaPlayer mp = MediaPlayer.create(appcontext, Uri.parse(file));  
mp.start();`*

### ***boolean StreamSoundBuff(int start, int line, byte[] buff, int len)***

Stream from PCM audio buffer or from RTP packets.

This function will stream the supplied audio buffer to the peer endpoint, transcoding if necessary.

Parameters:

- start: 1 for start or 0 to stop the playback
- line: specify the channel in case if there are multiple calls in progress (usually set to -1 for the current call if any)
- buff: audio buffer (raw PCM data or RTP packet)
- len: length of the buff (ideally it should be multiple of 360 if raw pcm or the size of the RTP packets which are to be passed separately)

Notes:



- The buff should not contain any file header if you are using raw PCM (only raw linear PCM audio data) or it should contain a full RTP packet (with the RTP header) if you are passing RTP data.
- You might set the “useaudiodevicerecord” parameter to “false” if you need streaming but don’t have an audio recorder device installed.
- If previously supplied buffer(s) are not completed yet, then the new one will be queued
- Alternatively you can use the `API_StreamSoundStream` function to pass an `InputStream` instead of buff and len.
- In case if you wish to receive the audio stream from the remote peer endpoint, see [this FAQ point](#) instead.

Buffer/stream format:

At least raw linear PCM is supported in the following format: PCM SIGNED 8000.0 Hz (8 kHz) 16 bit mono (2 bytes/frame) in little-endian (128 kbits). In case if your buffer is narrowband (8 kHz 16 bit mono), then the stream will be automatically converted to wideband if the VoIP audio codec is wideband such as opus or speex. In case if your buffer is wideband (16 kHz 16 bit mono) then you should set the `playbacksteamformat` parameter to `1` to allow auto conversion to narrowband if the VoIP audio codec is narrowband such as G.711 (PCMU, PCMA), G.729 or GSM.

The function can accept also RTP packets and will transcode them if necessary. Set the `streamsoundisrtp` parameter to `-1` to auto-guess raw PCM vs RTP (this is the default value), set to `0` if you supply raw PCM buffer or set to `1` if you supply RTP packets.

### ***boolean SetVolume(int dev,int volume)***

Set volume (0-100%) for the selected device.

The dev parameter can have the following values:

- 0 for the recording (microphone) audio device
- 1 for the playback (speaker) audio device
- 2 for the ringback (speaker) audio device

### ***int GetVolume(int dev)***

Return the volume (0-100%) for the selected device.

The dev parameter can have the following values:

- 0 for the recording (microphone) audio device
- 1 for the playback (speaker) audio device
- 2 for the ringback (speaker) audio device

### ***boolean SetIdle(boolean idle)***

You might use this API to further extend the battery life (above the usual phone power state changes).

The sipstack internally has an idle state which can be useful to decrease CPU and RAM usage by using less resources, slowing down all operations, running threads in low priority and increases internal timer intervals. This means that the app can enter in idle state even if running in foreground on a non-sleeping phone state (but with no user interaction and no important task running such as an ongoing call)

You should call this function with the idle parameter set to true if the screen is dimmed/off, there is no call and no user interaction with the application for a while. Call with the idle parameter set to false when the user begins any interaction with the application. The sipstack will also automatically disable the idle state when there is a new incoming call, chat or other important event that might require user interaction or CPU resources.

### ***String VAD()***

Returns voice activity statistics. See the VAD notification for more details.

For this to work you should set the vad parameter to at least 2 (4 for full report).

Note: if you call this function, VAD notifications will not be sent automatically anymore. (So you will need to continue to poll for the details).

More details [here](#)

### ***String RTPStat()***

Returns media statistics. See the RTPSTAT notification for more details.

For this to work you should set the vad parameter to at least 2 (4 for full report).

Note:

RTP statistics can be sent also automatically if you set the rtpstat parameter.

if you call this function, RTPSTAT notifications will not be sent automatically anymore

More details [here](#).

### ***string GetVersion()***

Return the program version number.

### ***String GetStatus(int line, int strict)***

Returns line status or global status if you pass -2 as line parameter. The possible returned texts are the same like for notifications (listed below).



If the strict variable is set to 1, then it will return “Unknown” if no such line is activated. If the strict variable is set to 0, then it will return the default active line if the line doesn’t exists.

*You should use the notifications described below to get the actual status of AJVoIP instead of continuously polling it with this function call.*

## ***String GetNotifications()***

Return the [notifications](#) from the SIP stack. You should poll for the notifications periodically from a separate thread. It will return accumulated events since the last function call (notifications separated by \r\n -CRLF).

More details [here](#).

Note:

- *We are using simple polling for this since Java doesn’t have function pointers to be used as a callback and other methods are either deprecated (Observer interface) or too complex (external libraries or sending the notifications on other channels such as a separate TCP stream or message queue).*
- *Once a notification string have been read then it will be cleared from the internal list, so it is guaranteed that you will never receive duplicates.*

## ***String GetNotificationsSync()***

Same as above, but will blocking wait for data (more efficient). You should call this only from a separate thread.

## ***boolean SetPushNotifications(int pushnotifications, String clientid, String packagename, String gateway)***

If you wish to use VoIP push notifications then you might use this function to have it assisted by the SIP SDK (otherwise you can implement it also separately in your code).

Parameters:

- pushnotifications: 0=disable,1=auto,2=direct,3=via gateway
- clientid: your app token (token ID or Project ID returned by registering to the notification service)
- packagename: the package name of your application to be used for push notification. If empty then it will be read from your app context. If using mizu push gateway then you might leave it empty or set to "com.mizuvoip.mizudroid.app"
- gateway: if your SIP server doesn’t support push notifications then you might use a gateway (the SIP stack will register also via this gateway)

To activate push notifications, first you will need to register to FCM from your own code as described [here](#) and [here](#).

Then once you call this function with the acquired client id, the SIP stack will begin to send push bind request (extra SIP headers or tags in the REGISTER requests using the protocol specified by [pushtype](#)).

This is required for the server side to learn your token and be able to send push notifications on incoming calls or chat.

The purpose of these notifications should be only to wake up your application if in background/sleeping mode, so it can start/register and process the incoming INVITE as normally. For chat message it should be enough if you just display the message and eventually store it (the user can launch your app by tapping on the displayed notification).

Start example: `SetPushNotifications(1, "TOKEN", "", "");`

Stop example: `SetPushNotifications(0, "", "", "");`

If you set the pushnotifications parameter to 1 (auto), then will try push with your server first (as described in RFC 8599 so your server must answer to REGISTER with Feature-Caps: \*;+sip.pns="fcm") and if fails then it will try via push gateway.

For more details read [here](#).

## ***int GetPushNotifications()***

Returns the push notification subscription state from the SIP stack. This should be used only if you let the SIP stack to handle the push notifications for you by calling the above SetPushNotifications API first.

Possible return values:

- 0: disabled (push notification disabled)
- 1: enabled unknown (might work)
- 2=success (push notification working)
- 3=failed (push notification subscription failed)

Note: you can assume that push notifications are working if you were capable to subscribe to FCM and get a valid token AND the GetPushNotifications function returns 2.

## ***Contacts***

Contact management has little to do with the SIP stack and should be handled entirely [by your application](#) (except presence status). You can use the above AJVoIP API to add VoIP functionality to your address book or contact list and based on the user presence you can display the different buttons with your design. Near each contact you can display a call/chat button which will launch a voip endpoint instance preconfigured with the actual contact (“callto” parameter). For the contact listing you can just use the native system phone-book or a separate contact list for your app if needed (or a mix of these).

For your convenience as an extra functionality the SDK also provides a simple contact management API which can be also used if for some reason you find it more suited for your needs, but in general we recommend to handle the contacts entirely in your own app since this task is more about user interface related development and less to do with the SIP specific API.

Contact parameters are stored as comma delimited strings with the following parameters:

imstatus,name,sip,phone,phone2,phone3,othernumbers,sipcontacturi,email,web,address,speeddial,extra,internalextra

#### **boolean SetContacts(String contacts)**

Set all contacts (contact parameters separated by new line)

#### **String GetContacts()**

Will return all contacts (in separated lines the parameters described above)

#### **boolean DelContact(String name)**

Delete contact.

#### **boolean AddContact(String params)**

Add a contact. Example: `Add_Contact('John Smith,jsmith,')`; //here we set only the name and the SIP fields

#### **boolean SetContact(String name, String params)**

Change contact.

#### **String GetContact(String name)**

Will return a single contact in the format described above.

Helper functions to set/get individual fields:

##### **boolean SetContactName(String name, String param)**

Set contact name.

##### **boolean SetContactSIP(String name, String param)**

Set contact sip uri.

##### **boolean SetContactPhone(String name, String param)**

Set contact phone number.

##### **boolean SetContactSpeedDial(String name, String param)**

Set contact speed dial number (short number).

##### **String GetContactName(String name)**

Get contact name.

##### **String GetContactSIP(String name)**

Get contact sip uri.

##### **String GetContactPhone(String name)**

Get contact phone number.

##### **String GetContactSpeedDial(String name)**

Get contact speed dial number (short number).

Example code for contact management can be found [here](#).

---

## **Presence**

Presence is based on SIP SIMPLE SUBSCRIBE/NOTIFY mechanism and it is used to detect the online status of the contacts.

There is no need to manage the contacts within SIP endpoint (as described above) to have presence functionality (so you can manage the contacts externally in your application).

The following steps are required:

1. Related settings:
  - enablepresence: 0/1
  - email = email address sent with contact info
  - presenceexpire = 3600
  - autoacceptpresencrequests = -1; //-1: not set (1), 0=auto reject all,1=ask for new users,2=yes, autoaccept new unknown users
2. First you should call PushContactlist to pass all the usernames and phonenumbers from your external contact list if any. This is necessary, because for existing contacts AJVoIP can accept the requests automatically, while for other it might ask for user permission
3. On first start you might call NumExists. If using the Mizu VoIP server, then it will return all existing contacts with SERVERCONTACTS,userlist notification where userlist are populated with the valid users and their online status.

4. Call CheckPresence(userlist). To save softswitch resources, you should carefully select the contacts. (Send only the contacts which are actually used and called numbers. We recommend up to 50 contacts. If the user select a contact, then you can call this function later with that single contact to request its status). *This function will start to send SUBSCRIBE requests.*
5. Use the SetPresenceStatus(statustring) function call to change the user online status with one of the followings strings: Online, Away, DND, Invisible , Offline (case sensitive) . *This function will start to send NOTIFY requests to subscribed parties.*
6. Once these are done, the following notifications can be received from java sip stack:  
NEWUSER,peerusername,displayname,email,URI  
PRESENCE,peerusername,status,displayname,email  
(displayname and email can be empty)

On newuser, you should ask the user if wish to accept it. If accepted, call the NewUser function. The same function should be called when the user adds a new contact to its contactlist.

For presence the following status strings are defined (be prepared to receive any of these and handle it with case insensitive by displaying red/green/gray/other icons):

- Open/Online/Reachable/Available/Call Me/Registered [GREEN]
- DND (Do not disturb; halt popups and sounds) [RED]
- Busy/Speaking (can be auto set) [ORANGE/YELLOW]
- Pending/Forwarding [ORANGE/YELLOW]
- Away/Idle [ORANGE/YELLOW]
- Close/Unreachable/Offline/Unregistered [GREY/WHITE]
- Unknown/Not Set [GREY/WHITE/NOCOLOR]
- Invisible (no status notifications will be sent) [GREY/WHITE/NOCOLOR]

Other suggestion for colors:

- red: busy/dnd
- bright green: online
- pale green: away/forwarding/pending
- white: user exists but unknown status or invisible
- no color: user doesn't exists / no presence feature

7. You might use the UnSubscribe() API to unsubscribe all endpoints (this includes presence, voicemail and BLF subscribes).

## BLF

BLF (Busy Lamp Field) can be used to monitor the state of an extension and it is implemented as SUBSCRIBE/NOTIFY with dialog event package as described in RFC 3265 and RFC 4235.

Set the **enableblf** parameter to enable/disable BLF. The following values are defined:

- 0: disable BLF
  - 1: auto (from here it will auto switch to 0 or 2 regarding the circumstances –whether BLF was initiated and succeed/failed)
  - 2: enable BLF
  - 3: force always (if you set to 3 then it can't be switched off later and will use BLF even after failure)
- Default value is 1.

To subscribe to other extensions call state, you can set the **blfuserlist** parameter or use the **CheckBLF(userlist)** to subscribe to other extension(s) state changes (users separated by comma). To remove an extension, just modify the blfuserlist parameter or call the DisableBLF(userlist) API.

Make sure that the other extension also has BLF support (so it can respond with NOTIFY for the BLF SUBSCRIBE).

Once the state of the remote extension(s) are changed, you will receive BLF notifications in this format:

**BLF,peerusername,direction,state,callid**

Fields:

- BLF: state header string
- peersusername: extension username
- direction
  - **undefined** (not for calls or no announced by the peer)
  - **initiator** (outgoing call)
  - **receiver** (incoming call)
- state
  - **trying** (call connect initiated)
  - **proceeding** (call connecting)
  - **early** (ringing or session progress)
  - **confirmed** (call connected)
  - **terminated** (call disconnected)
  - **unknown** (unrecognized call state received)
  - **failed** (BLF subscribe or notify failed)
- callid: optional value if reported from the remote extension (the SIP call-id of the call)

## Miscellaneous

Some other not so important API calls are listed below (helper functions):

#### **boolean Test()**

You might use this function to check the API availability. Should return true.

#### **boolean ServerInit(String address)** -deprecated

Call this function before to start any communication with this address (usually an IP number). This is required to release the Java security restrictions. Wait 1-2 second before calling the next function like Register or Call. This function is deprecated since v.3.8 (no need to call this, just call Register or others directly)

#### **boolean MightStop()**

It is a good practice to call this function when your app might be stopped or killed soon. For example your app/activity is pausing/closing/exiting and from there the OS might kill your process. This will just make sure that the internal SIP stack settings are properly saved and the sipstack is prepared for an unexpected termination.

#### **boolean Stop()**

Will stop all endpoints. This function call is optional when you unload AJVoIP from external app.

#### **boolean Exit()**

Will stop all endpoints and terminates the java sip application. This function call is optional when you unload the AJVoIP java module or wish to issue a forced termination. Its behavior can be controlled by the "exitmethod" parameter.

#### **boolean ReStart()**

Restart the SIP stack.

#### **void CheckConnection()**

You might call this function to quickly recover from connection failures on events not know by AJVoIP such as app switched to foreground or activity launch (otherwise AJVoIP should auto-recover from network failures)

#### **boolean CapabilityRequest(String server, String username)**

Will send an OPTION request to the server. Usually you should not use this function.

The server parameter can be empty if you already set it with other API calls or by parameter.

The username parameter can be empty (in this case the "From" address will be set to "unknown")

#### **String LineToCallID(int line)**

Get the SIP Call-ID for a line number.

#### **int CallIDToLine(String callid)**

Get the line number for a SIP Call-ID.

#### **boolean SetLineParameter(int line, String param, String value, int permanent)**

Set parameter for the current/next/all/specific line. Only some of the parameters are supported by this function (listed below).

These are advanced settings and this function might be used only if you need some specific/different behavior for a specific line only.

Otherwise, the behavior of the different lines are loaded from the global configuration (parameters), from the circumstances or can be influenced by the other API functions (try to use the other API's instead of this when possible).

Parameters:

Line: channel number.

If -2, then it will be set as global config like the API\_SetParameter.

If -1, then for the active line.

If 0, then it will be applied for all next/new channel(s).

Otherwise it will be applied for the specific line.

Param: settings key name

Value: value as string (or "NULL" to clear any old preset)

Permanent

If 1 then the setting will be kept for all future lines with the same line number

If 0 then the setting will be applied only for the current or very next channel with the same line

The following parameters are supported by this function:

peer (called number),address (will set both the serveraddress and proxyaddress),serveraddress,proxyaddress,

username,authusername,password,displayname,

voicerecording,muted,holded,maxsipmessagesize,codecretry,disccode,registerinterval,maxmsgresend,srtp\_suite,strictsrtp,dtmfmode,rtp\_timestamp,

rtp\_seq,rtp\_sscc,defpayload,setfinalcodec,presenceexpiresec,notifyexpiresec,sipproto,volumein,volumeout,volumering,videocalltype,videodirection,

keepvideosdponhold,defvideopayload,serverdomainandport,serveraddr,serverport,serverip,proxyport,proxyip,realm,

customsipheader,customsdffield,customsdpmfield,sip\_uui,sessionid,discreason,usesdpip,transport,line,callid,state

All preset settings for all lines can be removed by passing 0 for the line and empty or NULL for both the key and the value.

Examples:

```
mysipclient.SetLineParameter(1,"username", "mia",0); //set the username to mia for the next call on line 1
mysipclient.SetLineParameter(2,"username", "mia",1); //set the username to mia for all upcoming calls on line 2
mysipclient.SetLineParameter(2,"username", "NULL",1); //clear the permanently preset username from line 2
mysipclient.SetLineParameter(-1,"muted", "0",0); //unmute the current call (use the Mute API instead)
mysipclient.SetLineParameter(0,"muted", "4",0); //set the default muted state both side mute for the next call
mysipclient.SetLineParameter(0,"NULL", "NULL",1); //clear all the permanent settings from all lines
```

### boolean SetSIPHeader(int line, String hdr)

Set a custom sip header (a line in the SIP signaling) that will be sent with all messages. Can be used for various integration purposes to send auxiliary meta-data via the SIP signaling (for example for sending the http session id).

Example: `SetSIPHeader(-1, "X-MyData: VALUE");`

Multiple headers can be separated by CRLF (\r\n).

You can also set this with parameter (customsipheader).

### String GetSIPHeader(int line, String hdr)

Return a sip header value received by AJoIP. If not found it will return a string beginning with "ERROR:" such as "ERROR: no such line".

### boolean SetUUI(int line, String value, int fortarget)

Set a custom UUI (User-to-User Call Control Information as described in RFC 7433).

Value is the UUI data (with or without parameters)

Fortarget specifies if the UUI have to be sent to target party with call transfer or redirect escaped. 0: no (to peer with the User-to-User header), 1: yes (to target in Contact or Refer-To URI), 2: both.

Example:

`SetURI(-1, "anydata",-2);`

`SetURI(-1, "DATA;encoding=hex;purpose=foo;content=bar",-2);`

You can also set this with the sip\_uui parameter.

### boolean SetSDPField (int line, String field, int type)

Set a custom SDP field (a line in the SDP body) that will be sent with all messages.

Set the type parameter to 0 for global values (before the m= line) or 1 for media values (after the m= line).

Example: `SetSDPField(-1, "a=3ge2ae:requested",1);`

Multiple headers can be separated by CRLF (\r\n). You can also set this with the [customsdpfield](#) and [customsdpmediafield](#) parameters.

*Line -2 means all lines, -1 means current active line or use 1+ means for an existing line in call.*

*You can set a SIP header for the next call by using line number -3 or clear the old header(s) by using line number 0.*

### Boolean RTPHeaderExtension (int line, int profile, String extension)

Set [RTP header extension](#) for the RTP packets.

The profile will be set as the first two bytes in the extension header (might be used as a custom identifier or parameter).

The extension can be one or multiple numbers separated by semicolon (;). These numbers will be sent as 32 bit words with the RTP header extension payload.

Example: `RTPHeaderExtension (-1, 1, "987");` //will set the profile number to 1 and the rtp extension word to 987 for the current call

*Line -2 means all lines, -1 means current active line or use 1+ means for an existing line in call.*

*You can set a SIP header for the next call by using line number -3 or clear the old header(s) by using line number 0.*

*Set the profile to 0 and the extension string to empty to clear it.*

### boolean ED137PTT (int line, int ptt, int pttid)

ED-137 Push to talk.

Parameters:

- line: channel number
- ptt: 0: off (not speaking), 1: on (Normal PTT ON), 2: Coupling PTT ON, 3: Priority PTT ON, 4: Emergency PTT ON
- pttid: optional PTT-ID (otherwise loaded from global config)

Will return true if initiated successfully or false on failure.

The [ed137](#) parameter should be set to 1 before using this function. See the [ED 137 guide](#) for more details

### boolean SendSIPMessage(int line, String msg, String body, String account)

Send a custom SIP signaling message (for example OPTIONS, NOTIFY, etc).

Parameters:

- line: endpoint where the message will be sent. -3: new endpoint, -2: all endpoints, -1: current active, 0: register endpoint, 1+: call [channel number](#)
- msg: SIP message to send. It can be just the method name (OPTIONS,MESSAGE,NOTIFY,INVITE,etc), the full message header or the full message including also a body (such as SDP)
- body: optional SIP message body (such as SDP, xml payload or chat text, etc). Set to "null" if body must not be sent.
- account: optional SIP account details if you wish to use other parameters then the configured one. same format like the [extraregisteraccounts](#) parameter

Examples:

- Send a custom REGISTER request: `mysipclient.SendSIPMessage(0, "fullmessagehere", "", "");`
- Send UPDATE on line 1: `mysipclient.SendSIPMessage(1, "UPDATE", "", "");`
- Send OPTIONS on a new line to another server: `mysipclient.SendSIPMessage(-3, "OPTIONS", "", "otherserveraddress.com:port,username,password");`
- Send PUBLISH with a custom body: `mysipclient.SendSIPMessage(-3, "PUBLISH", "anymessagehere", "");`

**String GetSIPMessage(int line, int dir, int type)**

Return the last received or sent SIP signaling message as raw text.

Dir:

- 0: in (incoming/received message)
- 1: out (outgoing/sent message)

Type:

- 0: any
- 1: SIP request (such as INVITE, REGISTER, BYE)
- 2: SIP answer (such as 200 OK, 401 Unauthorized and other response codes)
- 3: INVITE (the last INVITE received or sent)
- 4: the last 200 OK (call connect, ok for register or other)

**String GetLastRecInvite()**

Return the last received INVITE message.

**String GetLastRecSIPMessage(String line)**

Get the last received SIP message as clear text. Line is the line number or the SIP call id.

**String GetLastRecFileName (String line)**

Returns the last recorded file name.

**String SendChatIsComposing (String line, String number)**

Send typing notification.

**String GetAddress()**

Return the local SIP listener address (IP:port)

**boolean IsOnline()**

Return true if network is present

**boolean IsRegistered()**

Return true if AJVoIP is registered ("connected") to the SIP server.

**int IsRegisteredEx()**

Returns extended registration state: 0=unknown,1=not needed,2=yes,3=working yes,4=working unknown,5=working no,6=unregistered,7=no (failed)

**int IsInCall()**

Return whether the sip stack is in call: 0=no,1=ringing,2=speaking

**boolean IsIncomingVideo()**

Return true if the current incoming call has video offer or false if it has only audio offer

Example code:

```
if(mysipclient.IsIncomingVideo()) //check incoming call type
{
    //auto accept video call
    mysipclient.AcceptVideo(fragmentResId, fragmentinstance);
}
else
{
    //auto accept audio call
    mysipclient.Accept(-1);
}
```

**int GetCurrentConnectedCallCount()**

Get number of current connected calls

**String GetRegFailReason(boolean extended)**

Will return a text about the reason of the last failed registration. Set the extended parameter to true to get more details

**String GetDiscReasonText()**

Return the disconnect reason of the last disconnected call.

**int GetAccountRegState(String domain, String proxy, String username, String sipusername, boolean pushnotify, boolean strict)**

Query account register state. Useful if you are using multiple accounts.

Returns -1: no such account register ep, 0: working, 1: success, 2: failed, 3: unregistered.

Parameters domain, proxy, username, sipusername will be used to match the account.

If the pushnotify is true, then it will look after push register endpoints (useful if push via gateway).

If the strict parameter is false, then will check the best matching account after the passed parameters.

If the strict parameter is true, then will enforce exact parameter match when checking after the endpoints (server domain/username/etc).

**String GetAccountRegStateString(String domain, String proxy, String username, String sipusername, boolean pushnotify, boolean strict)**

Query account register state. Useful if you are using multiple accounts.

Return status text (for example "Registered" if the account is registered to the server).

Parameters domain, proxy, username, sipusername will be used to match the account.

If the pushnotify is true, then it will look after push register endpoints (useful if push via gateway).

If the strict parameter is false, then will check the best matching account after the passed parameters.

If the strict parameter is true, then will enforce exact parameter match when checking after the endpoints (server domain/username/etc).

**String GetCallerID(int line)**

Will return the remote party name

**String GetIncomingDisplay(int line)**

Get incoming caller id (might return two lines: caller id \n caller name)

**String GetLastCallDetails()**

Get details about the last finished call.

**String GetMySIPURI(boolean all)**

Will return the SIP URI on which the current endpoint can be reached such as [username@server.com](mailto:username@server.com) or username@localip:port.

If all is true, then it will return all possible URI's separated by comma.

**void AddLog(String msg)**

Add a message to AJVoIP log.

**boolean HoldChange(int line)**

Same as Hold, but without the second parameter. This call will always invert the hold status for an endpoint (If the call was active, then it will switch to held status and if the call was in hold, then it will reactivate it).

**String VAD()**

Returns voice activity statistics. See the VAD notification for more details.

Note: if you call this function, VAD will not be sent automatically anymore. (So you will need to continue to poll for the details).

**String HTTPGet(String url)**

Send a HTTP GET request. Check if return string begins with "ERROR".

Note:

You should never call http requests from your main GUI thread, otherwise it will fail with a NetworkOnMainThreadException exception (This exception will occur only internally, not thrown to you).

For development, you might remove the restriction:

```
StrictMode.ThreadPolicy policy = new StrictMode.ThreadPolicy.Builder().permitAll().build();
```

```
StrictMode.setThreadPolicy(policy);
```

**boolean HTTPPost(String url, String data)**

Send a HTTP POST request.

You should not call this function from your main GUI thread.

**String HTTPReq(String url, String data)**

Send a HTTP POST or GET request. (If data is empty, then GET will be sent). Can be tunneled. Can block for up to 20 seconds.

You should not call this function from your main GUI thread.

**boolean HTTPReqAsync(String url, String data)**

Send a HTTP POST or GET request. (If data is empty, then GET will be sent). Can be tunneled. The result will be returned in notifications with "ANSWER" header.

It is safe to call this function also from the main GUI thread.

**boolean SaveFile(String filename, String content)**

Will save the text file to local disk AJVoIP working directory in encrypted format (use SaveFileRaw to save as-is)

**String LoadFile(String filename)**

Load file from local disk.

**boolean SaveFileRemote(String filename, String content)**

Save file to remote storage (preconfigured ftp or http server )

**boolean LoadFileRemote(String filename)**

Load file from remote storage. The download process is performed asynchronously. You need to call this function only once and then a few seconds later call the LoadFile function with the same file name. It will contain "ERROR: reason" text if the download failed.

#### **String LoadFileRemoteSync(String filename)**

Will download the specified file from remote storage synchronously (will block until done or fails).

#### **String GetBlacklist()**

Get blacklist

#### **boolean SetBlacklist(String str)**

Set whole blacklist (users/numbers separated by comma)

#### **boolean AddToBlacklist(String str)**

Add to blacklist

#### **boolean ClearCredentials()**

Clear existing user account details.

#### **boolean DelSettings (int level)**

Delete settings and data. Levels: 0: nothing, 1: settings, 2: everything

#### **int IsEncrypted ()**

Returns whether the connection is encrypted. -1: unknown, 0=no,1=partially/weak yes,2=yes,3=always strong

#### **String GetLogs()**

Can be used to get the logs (which are otherwise written also to standard output and to Logcat)

#### **String GetBindir()**

Returns the application path (folder with the app binaries or app home folder)

#### **String GetWorkdir()**

Returns the application working directory (data folder).

Based on:

```
appcontext.GetFilesDir().getPath();  
Environment.getDataDirectory().getPath();
```

#### **String GetAltWorkdir()**

Returns the application alternative working directory (such as folder on external SD card).

#### **int ShouldReset()**

Check if the sipstack should be restarted. Usually this is required only on local network change (such as IP change or changing from mobile data to wifi).

Possible return values: 0=no,1=not registered for a while,2=network changed

#### **boolean ShouldResetBeforeCall()**

This function might be called before calls and you should quickly restart the sipstack if returns true (the continue to make the call).

#### **boolean RecFiles\_Del()**

Delete local recorded files.

#### **boolean GetDeviceID()**

Returns an unique device ID.

#### **String GetVersion()**

Return the program version number.

Most of the API functions were covered above in this guide, however you might find also some additional helper functions exposed. You should be able to cover all your needs using the above functions and most of the additional API's are redundant or needed only in very special circumstances.

See the [Javadoc](#) for a complete listing of all public functions.

## **Notifications**

Notifications can be received by the [GetNotifications](#) or [GetNotificationsSync](#) API calls.

Usually you will have to parse the received strings from your code. The parameters are separated by comma ','. First you have to check the first parameter (until the first comma) to determine the event type. Then you have to check for the other parameters according to the specification below.

Please note that you can get more than one event at once, separated by newline (or ,NEOL \r\n) so you should check for new lines first and then parse all events.

Notifications might be prefixed with the "WPNOTIFICATION," string (you should handle and remove this before parsing the rest of the line).

A code example can be found [here](#).

The easiest way to get started is to just log out all messages at first and from there the usage should be more obvious.



### Line parameter:

Most of the messages contains a line parameter which is set to -1 for the global state or 0,1,2,3... for the individual lines. For this reason you might see duplicated notifications: one sent for the global state, another sent for the actual line state.

For you wish to implement something basic, then it is enough of you check the notifications only for the global state and ignore the line states.

If you wish to handle [multi-lines explicitly](#) then you should check also the state of the individual lines (you might ignore the notifications about global state in this case).

The following messages are defined:

---

***STATUS,line,statustext,peername,localname,endpointtype***

---

You will receive STATUS notifications when the SIP session state is changed (SIP session state machine changes) or periodically even if there was no any change. The STATUS notification looks like this:

**STATUS,line,statustext,peername,localname,endpointtype,peerdisplayname,[callid],online,registered,incall,mute,hold,encrypted,video,group,rtpsent,rtprec,rtploss,rtplosspercet,serverstats**

The line parameter can be -1 for general status or a positive value for the different lines.

General status means the status for the “best” endpoint.

This means that you will usually see the same status twice (or more). Once for general sip client status and once for line status.

For example you can receive the following two messages consecutively:

**STATUS,1,Connected,peername,localname,endpointtype,peerdisplayname,[callid],...**

**STATUS,-1,Connected**

You might decide to parse only general status messages (where the line is -1), messages for specific line (where line is zero or positive) or both.

Status notifications are sent on state change but also at a regular interval (so you can see the same notification again and again even if there was no state change).

The following **status** values are defined **for general status (line set to -1)**:

- Starting...
- Idle.
- Ready
- Register...
- Registering... (or “Register...”)
- Register Failed
- No network
- Not Registered
- Registered (or “Registered.”)
- Unregistered
- Accept
- Starting Call
- Call
- Call Initiated
- Calling...
- Ringing...
- Incoming...
- In Call (xxx sec)
- Hangup
- Call Finished
- Chat (or Messaging)

*Note: general status means the “best” status among all lines. For example if one line is speaking, then the general status will be “In Call”.*

The following **status** values are defined **for individual lines** (line set to a positive value representing the channel number starting with 1):

- Unknown (you should not receive this)
- Init (voip library started)
- Ready (sip stack started)
- Outband (notify/options/etc. you should skip this)
- **Register** (from register endpoints) (or “Register...” or “Registering...”)
- Unregister
- Subscribe (presence)
- Chat (IM)
- **CallSetup** (one time event: call begin)
- Setup (call init)
- InProgress (call init)
- Routed (call init)
- Ringing (SIP 180 received or similar)

- **CallConnect** (one time event: call was just connected)
- InCall (call is connected)
- Muted (connected call in muted status)
- Hold (connected call in hold status)
- Speaking (call is connected)
- Midcall (might be received for transfer, conference, etc. you should treat it like the Speaking status)
- **CallDisconnect** (one time event: call was just disconnected)
- Finishing (call is about to be finished. Disconnect message sent: BYE, CANCEL or 400-600 code)
- Finished (call is finished. ACK or 200 OK was received or timeout)
- Deletable (endpoint is about to be destroyed. You should skip this)
- Error (you should not receive this)

You will usually have to display the call status for the user, and when a call arrives you might have to display an accept/reject button. For simplified call management, you can just check for the one-time events (CallSetup, CallConnect, CallDisconnect)

**Peername:** the other party username (if any)

**Localname:** the local user name (or username).

**Endpointtype:** is 1 from client endpoints (outbound) and 2 from server endpoints (inbound).

**Peerdisplayname:** the other party display name if any

**CallID:** SIP session id (SIP call-id) in [square brackets]

**Online:** network status. 0 if no network or internet connection, 1 if connectivity detected (always the global status)

**Registered:** registration state. 0=unknown,1=not needed,2=yes,3=working yes,4=working unknown,5=working no,6=unregistered, 7+ =no (failed) (always the global status)

**InCall:** phone/line is in call. 0=no,1=setup or ringing,2=speaking

**Mute:** is muted status. 0=no,1=undefined,2=hold,3=other party hold,4=both in hold (or if you wish to simplify: 0 means no, others means yes)

**Hold:** is on hold status: 0=no,1= undefined,2=hold,3=other party hold,4=both in hold (or if you wish to simplify: 0 means no, others means yes)

**Encrypted:** encryption status: -1: unknown, 0=no,1=partially/weak yes,2=yes,3=always strong (or if you wish to simplify: 0 and -1 means no, others means yes)

**Video:** set to 1 for video calls (with video media offer). Otherwise 0.

**Group:** group string for group chat and conference calls (members separated by | )

**RTPSent:** number of sent RTP packets (only if endpoint is in call)

**RTPRec:** number of received RTP packets (only if endpoint is in call)

**RTPLoss:** number of lost RTP packets (only if endpoint is in call)

**RTPLossPercent:** percent of the lost RTP packets (only if endpoint is in call)

**ServerStat:** RTP statistics received from the server, if any (only if endpoint is in call)

For example the following status means that there is an incoming call ringing from 2222 on the first line:

**STATUS,1,Ringing,2222,1111,2,Katie,[callid]**

The following status means an outgoing call in progress to 2222 on the second line:

**STATUS,2,Speaking,2222,1111,1,[callid]**

To display the “global” phone status, you will have to do the followings:

1. Parse the received string (parameters separated by comma)
2. If the first parameter is “STATUS” then continue
3. Check the second parameter. If “-1” continue otherwise nothing to do
4. Display the third parameter (Set the caption of a custom control)
5. Depending on the status, you might need to do some other action. For example display your “Hangup” button if the status is between “Setup” and “Finishing” or popup a new window on “Ringing” status if the endpointtype is “2” (for incoming calls only; not for outgoing)

If the “stats” is on (set to a value higher than 0) then you will receive periodic status messages during calls (might be useful if you are interested in RTP statistics during a call).

---

### ***PRESENCE,peername,state,details,displayname,email***

This notification is received for presence changes (peers online status).

Line: used phone line

Peername: username of the peer

State and details: presence status string; one of the followings:

CallMe,Available,Open,Pending,Other,CallForward,Speaking,Busy,Idle,DoNotDisturb,DND,Unknown,Away,Offline,Closed,Close,Unreachable,Unregistered,Invisible,Exists,NotExists,Unknown,Not Set

Displayname: peer full name (it can be empty)

Email: peer email address (it can be empty)

#### Notes for the state and details fields:

One of these fields might be empty in some circumstances and might not be a string in the above list (especially the details).

The **details** field will provide a more exact description (for example “Unreachable”) while the **state** field will provide a more exact one (for example “Close”). For this reason if you have a presence control to be changed, check the **details** string first and if you can’t recognize its content, then check the **state** string. For displaying the state as text, you should display the **details** field (and display the **state** field only if the **details** string is empty).

---

### **DTMF,line,msg**

Incoming DTMF notification.

Msg is a string parameter representing the incoming DTMF digit. Usually one of the followings: 0123456789\*#ABCD

Supported dtmf methods: SIP INFO and RFC2833

Example: **DTMF,1,7** (dtmf digit “7” received on first line)

---

### **INFO,type,line,peername,text**

Notifications about incoming/outgoing [INFO](#) or [DTMF](#) messages.

*Note: for incoming DTMF you should watch for the above described DTMF notification instead of this! DTMF notification will be triggered even if the message was received with SIP INFO.*

Parameters:

Type: The possible values for the type parameter is the following:

ERROR: Outgoing DTMF (API\_Dtmf) or INFO (API\_Info) message failed

WARNING: Outgoing DTMF failover from SIP INFO to RFC 2833 or In-Band on answer timeout or error response

OK: Outgoing DTMF (API\_Dtmf) or INFO (API\_Info) was sent successfully

REC: Incoming INFO message receive. Note that if the incoming message is a dtmf digit, then a DTMF notification will be triggered instead of INFO

Line: Phone line

Peername: Other party username

Text: INFO message body when type is REC or any additional info if type is ERROR, WARNING or OK.

Examples:

**INFO,ERROR,1,1111,timeout** (on API\_Dtmf or API\_Info message send failed to 1111 on line 1)

**INFO,WARNING,1,1111,failback to rfc2833** (on API\_Dtmf failback from INFO to rfc2833 or in-band)

**INFO,OK,1,1111** (on API\_Dtmf or API\_Info message sent successfully to 1111 on line 1)

**INFO,REC,1,1111,hello** (on SIP INFO message received from 1111 which is not DTMF)

*Note:*

*When sending DTMF in RTP (inband or rfc2833) then it is not possible to get feedback whether the message was actually delivered. In this case you will receive an INFO,OK when the message send was initiated successfully. Otherwise if SIP INFO is used, then you will receive INFO,OK only on 2xx answer from the server or the other peer.*

---

### **BLF,peerusername,direction,state,callid**

This notification is received for incoming BLF messages.

Described in the BLF section above.

---

### **USSD,line,status,text**

This notification is received about incoming USSD messages or report about success/failure about the outgoing USSD messages sent by [SendUSSD](#).

Line: the session line

status: 0: send failed, 1: send succeeded, 2: received

text: text is the received USSD string (if status is 2) otherwise it might contain an error (if status is 0)

---

### **CHAT,line,peername,text**

This notification is received for incoming chat messages.

Line: used phone line

Peername: username of the peer

Text: the chat message body

*Note:*

- The chat actually could be an incoming SMS message (for example a 3GPP SMS payload)
- If the text begins with “\_BASE64\_” then you must base64 decode the rest of the string before presenting it to the user.
- If the text begins with “GROUP:” then it is a group chat. Example: “GROUP Katie,John: hi”. In this case you might remove the header (until the second colon) and display the message in a separate thread.

---

### **CHATREPORT,line,peername,status,statustext,group,md5**

Chat transmission status report so you can process if outgoing message deliver was successfully or failed.

Line: used phone line  
Peername: username of the peer  
Status: 1 means sending in progress, 2 means successfully sent, 3 means failed  
Statustext: error text if any  
Group: optional parameter for group chat (member names separated by | )  
MD5: the MD5 checksum of the message text

Note:

If the offline messaging is not disabled (offlinechat parameter is not set to 0) then AJVoIP can retry later (on next start and/or when any SIP request is received from the target user) reporting status 4 instead of 3 on failed delivery. The MD5 checksum in this case will be calculated from concatenated pending message text and not for the last message.

---

**CHATCOMPOSING, line, peername, status**

Chat “is composing” notifications.

Line: used phone line  
Peername: username of the peer  
Status: 1 means other party is typing, 2 means other party is idle or stopped typing

---

**CDR, line, peername, caller, called, peeraddress, connecttime, duration, discparty, reasontext**

After each call, you will receive a CDR (call detail record) with the following parameters:

Line: used phone line  
Peername: other party username, phone number or SIP URI  
Caller: the caller party name (our username in case when we are initiated the call, otherwise the remote username, displayname, phone number or URI)  
Called: called party name (our username in case when we are receiving the call, otherwise the remote username, phone number or URI)  
Peeraddress: other endpoint address (usually the VoIP server IP or domain name)  
Connecttime: milliseconds elapsed between call initiation and call connect  
Duration: milliseconds elapsed between call connect and hangup (0 for not connected calls. Divide by 1000 to obtain seconds.)  
Discparty: the party which was initiated the disconnect: 0=not set, 1=AJVoIP, 2=peer, 3=undefined  
Disconnect reason: a [text](#) about the reason of the call disconnect (SIP disconnect code, CANCEL, BYE or some other error text)

---

**VREC, line, stage, type, path, reason**

Voice upload status (for voice recording / call recording).

line: channel number (*note: with stage 3 and 4 it will always report -1 or -2 means default/not specified*)  
stage: 0:disabled, 1:call record begin, 2:upload begin, 3: upload success, 4: upload fail (*note: stage 0 might not be reported*)  
type: upload method: 0: unknown, 1: local file, 2: ftp, 3: http, 4: server  
path: upload path/file (*note: if stage is 1 then type and path is not reported yet*)  
reason: failure reason (*if stage is 4*)

---

**VAD, parameters**

Voice activity.

This is sent in around every 2000 milliseconds (2 seconds) by default (configurable with the vadstat\_ival parameter in milliseconds) if you set the “vadstat” parameter to 3 or it can be requested by VAD. Also make sure that the “vad” parameter is set to at least “2”.  
This notification can be used to detect speaking/silence or to display a visual voice activity indicator.

Format:

VAD, local\_vad: ON local\_avg: 0 local\_max: 0 local\_speaking: no remote\_vad: ON remote\_avg: 0 remote\_max: 0 remote\_speaking: no

Parameters:

local\_vad: whether VAD is measured for microphone: ON or OFF  
local\_avg: average signal level from microphone  
local\_max: maximum signal level from microphone  
local\_speaking: local user speak detected: yes or no

remote\_vad: whether VAD is measured from peer to speaker out: ON or OFF  
remote\_avg: average signal level from peer to speaker out  
remote\_max: maximum signal level from peer to speaker out  
remote\_speaking: peer user speak detected: yes or no

## ***RTPSTAT,quality,sent,rec,issues,loss***

Media quality reports.

Can be enabled by the [rtpstat](#) parameter.

The parameters are calculated since the last RTPSTAT notification (for the past x seconds).

Parameters:

- Quality: quality points between 0 and 5. The calculations considers many factors such as RTP issues, RTCP reports, codec problems, packet loss, packet delay, jitter and processing delay.  
The following values are defined:
  - 0: no audio or non-recognizable voice
  - 1: very bad quality
  - 2: bad quality
  - 3: medium quality
  - 4: good quality
  - 5: excellent quality
- Sent: RTP packets sent
- Rec: RTP packets received and played
- Issues: number of issues (any issues are counted, such as sequence number mismatch or packet drop)
- Loss: lost packets

More details [here](#).

## ***GROUP,line,peers***

Sent for conference calls. You might update the displayed peer name with the peers strings received here.

The peers parameter is the list of members separated by |. For example: Kate | John | Linda

## ***START,what***

This message is sent immediately after startup (so from here you can also know that the SIP engine was started successfully).

The what parameter can have the following values:

“api” -api is ready to use

“sip” -sipstack was started

## ***STOP,api***

This message is sent when the SIP stack is terminated/destroyed.

## ***SHOULDRESET,reason text***

You should restart AJVoIP (or reinit the library) when you receive this notification.

This is usually sent when network was changed (connection type, IP address), thus it might be best to reinitialize the whole SIP stack to recalculate the optimized environment variables. The message is not sent while in call.

## ***LINE,number***

This message is sent when the active line is changed.

## ***EVENT,TYPE,txt***

Important events which should be displayed for the user.

The following TYPE are defined: EVENT, WARNING, ERROR

This means that you might receive messages like this:

WPNOTIFICATION,EVENT,EVENT,any text NEOL \r\n

These messages will be received only if you set the “events” parameter to 2. (by default is set to 2)

## ***POPUP,txt***

Should be displayed for the users in some way (hint/toast).

Example: Toast.makeText(appcontext, txt, Toast.LENGTH\_LONG).show();

## *LOG,TYPE,txt*

Detailed logs (may include SIP signaling).

The following TYPE are defined: EVENT, WARNING, ERROR

These messages will be received only if you set the “events” parameter to 3. (by default is set to 2)

## *LOG,RTP,txt*

RTP statistics.

Example: RTP: sent 15695 lasts: 0 (p2p: 0 sdp: 0 rrp: 15695 tnl: 15701), rec: 17281 lastr: 0, loss: 201 1%, cpu: 0.0%, cpurel: 0.0% (0.0), srvsent: 10326 srvrec: 10302 srvloss: 10 0%

## *Other notifications*

Format: messageheader, messagetext. The followings are defined:

“**START**” [api/sip]. You should start to call the API only after you receive the START,api notification.

“**CREDIT**” messages are received with the user balance status if the server is sending such messages.

“**RATING**” messages are received on call setup with the current call cost (tariff) or maximum call duration if the server is sending such messages.

“**MWI**” messages are received on new voicemail notifications if you have enabled voicemail and there are pending new messages

“**PRESENCE**” peer online status

“**SERVERCONTACTS**” contact found at local VoIP server

“**NEWUSER**” new user request

“**ANSWER**” answer for previous request (usually http requests)

## *Example session*

Here is how the notifications looks like in a typical session (start, register, make a call, hangup, terminate):

WPNOTIFICATION,START,api,NEOL

WPNOTIFICATION,START,sip,NEOL

WPNOTIFICATION,STATUS,-1,Initialized,NEOL

WPNOTIFICATION,STATUS,-1,Register...,NEOL

WPNOTIFICATION,EVENT,EVENT,Connecting...,NEOL

WPNOTIFICATION,STATUS,-1,Registering...,NEOL

WPNOTIFICATION,STATUS,0,Registering,istvantest2,istvantest2,1,voip.mizu-voip.com,[2e1123294504249584311k49333rmwp],,1,4,0,0,0,0,NEOL

WPNOTIFICATION,CREDIT,Credit: 4.2 USD,NEOL

WPNOTIFICATION,STATUS,-1,Registered.,NEOL

WPNOTIFICATION,EVENT,EVENT,Authenticated successfully. [ep: 0 2e1123294504249584311k49333rmwp Registering 12538],NEOL

WPNOTIFICATION,STATUS,0,Registered,istvantest2,istvantest2,1,voip.mizu-voip.com,[2e1123294504249584311k49333rmwp],,1,2,0,0,0,0,NEOL

WPNOTIFICATION,STATUS,-1,Starting call to testivr3,NEOL

WPNOTIFICATION,EVENT,EVENT,call [wpmain],NEOL

WPNOTIFICATION,STATUS,-1,Call,NEOL

WPNOTIFICATION,STATUS,-1,Call Initiated,NEOL

WPNOTIFICATION,STATUS,1,CallSetup,testivr3,istvantest2,1,testivr3,0,0,0,100,,[6e4351661777543861707k49334rmwp],1,2,1,0,0,0,NEOL

WPNOTIFICATION,STATUS,1,Routed,testivr3,istvantest2,1,testivr3,[6e4351661777543861707k49334rmwp],,1,2,1,0,0,0,NEOL

WPNOTIFICATION,STATUS,1,InProgress,testivr3,istvantest2,1,testivr3,[6e4351661777543861707k49334rmwp],,1,2,1,0,0,0,NEOL

WPNOTIFICATION,STATUS,-1,Calling...,NEOL

WPNOTIFICATION,STATUS,1,Ringing,testivr3,istvantest2,1,testivr3,[6e4351661777543861707k49334rmwp],,1,2,1,0,0,0,NEOL

WPNOTIFICATION,STATUS,-1,Ringing...,NEOL

WPNOTIFICATION,STATUS,1,CallConnect,testivr3,istvantest2,1,testivr3,0,0,0,100,,[6e4351661777543861707k49334rmwp],1,2,2,0,0,0,NEOL

WPNOTIFICATION,STATUS,1,Speaking,testivr3,istvantest2,1,testivr3,[6e4351661777543861707k49334rmwp],,1,2,2,0,0,0,NEOL

WPNOTIFICATION,STATUS,-1,Speaking (0 sec),NEOL

WPNOTIFICATION,STATUS,-1,Hangup,NEOL

WPNOTIFICATION,STATUS,-1,Speaking (2 sec),NEOL

WPNOTIFICATION,EVENT,EVENT,hangup [wpmain],NEOL

WPNOTIFICATION,STATUS,1,CallDisconnect,testivr3,istvantest2,1,testivr3,98,98,0,100,,[6e4351661777543861707k49334rmwp],1,2,0,0,0,0,NEOL

WPNOTIFICATION,STATUS,-1,Call Finished,NEOL

WPNOTIFICATION,CDR,1,testivr3,istvantest2,testivr3,voip.mizu-voip.com,1499,1969,1,User Hung Up (exD),[6e4351661777543861707k49334rmwp],NEOL

WPNOTIFICATION,STATUS,1,Finishing,testivr3,istvantest2,1,testivr3,[6e4351661777543861707k49334rmwp],,1,2,0,0,0,0,NEOL

WPNOTIFICATION,EVENT,EVENT,Call duration: 2 sec [ep: 1 6e4351661777543861707k49334rmwp Finishing 12538],NEOL  
WPNOTIFICATION,STATUS,1,Finished,testivr3,istvantest2,1,testivr3,[6e4351661777543861707k49334rmwp],,1,2,0,0,0,0,NEOL  
WPNOTIFICATION,STATUS,-1,Registered.,NEOL  
WPNOTIFICATION,STOP,api,NEOL

### *Parse notifications code example*

Below is a short code snippet demonstrating basic notification parsing.

Notifications handling is all about a bit of string parsing so maybe better if you just implement it from scratch so you will be more familiar with your own logic then the string handling practices in this example code.

In this example we assume that we [receive the notifications](#) in a function called ProcessNotifications.

```
public void ProcessNotifications(String receivednot)
{
    if (receivednot == null || receivednot.length() < 1) return;

    // we can receive multiple notifications at once, so we split them by CRLF or with ",NEOL \r\n" and we end up with a
    String array of notifications
    String[] notarray = receivednot.split(",NEOL \r\n");
    for (int i = 0; i < notarray.length; i++)
    {
        String notifywordcontent = notarray[i];
        if (notifywordcontent == null || notifywordcontent.length() < 1) continue;
        notifywordcontent = notifywordcontent.trim();
        notifywordcontent = notifywordcontent.replace("WPNOTIFICATION,", "");

        // now we have a single notification in the "notifywordcontent" String variable
        Log.v("AJVOIP", "Received Notification: " + notifywordcontent);

        int pos = 0;
        String notifyword1 = ""; // will hold the notification type
        String notifyword2 = ""; // will hold the second most important String in the STATUS notifications, which is the
        third parameter, right after the "line" parameter

        // First we are checking the first parameter (until the first comma) to determine the event type.
        // Then we will check for the other parameters.
        pos = notifywordcontent.indexOf(",");
        if(pos > 0)
        {
            notifyword1 = notifywordcontent.substring(0, pos).trim();
            notifywordcontent = notifywordcontent.substring(pos+1, notifywordcontent.length()).trim();
        }
        else
        {
            notifyword1 = "EVENT";
        }

        // Notification type, "notifyword1" can have many values, but the most important ones are the STATUS types.

        // After each call, you will receive a CDR (call detail record). We can parse this to get valuable information
        about the latest call.
        // CDR,line, peername,caller, called,peeraddress,connecttime,duration,discparty,reasonstext
        // Example: CDR,1, 112233, 445566, 112233, voip.mizu-voip.com, 5884, 1429, 2, bye received
        if (notifyword1.equals("CDR"))
        {
            String[] cdrParams = notifywordcontent.split(",");
            String line = cdrParams[0];
            String peername = cdrParams[1];
            String caller = cdrParams[2];
            String called = cdrParams[3];
            String peeraddress = cdrParams[4];
            String connecttime = cdrParams[5];
            String duration = cdrParams[6];
            String discparty = cdrParams[7];
            String reasonstext = cdrParams[8];
        }
        // lets parse a few STATUS notifications
        else if(notifyword1.equals("STATUS"))
        {
            //ignore line number. we are not handling it for now
            pos = notifywordcontent.indexOf(",");
            if(pos > 0) notifywordcontent = notifywordcontent.substring(pos+1, notifywordcontent.length()).trim();

            pos = notifywordcontent.indexOf(",");
            if(pos > 0)
            {
                notifyword2 = notifywordcontent.substring(0, pos).trim();
```

```

        notifywordcontent = notifywordcontent.substring(pos+1, notifywordcontent.length()).trim();
    }
    else
    {
        notifyword2 = notifywordcontent;
    }

    if (notifyword2.equals("Registered."))
    {
        // means the SDK is successfully registered to the specified VoIP server
    }
    else if (notifyword2.equals("CallSetup"))
    {
        // a call is in the setup stage
    }
    else if (notifyword2.equals("Ringing"))
    {
        // check the other parameters to see if it an incoming call and display an alert for the user
    }
    else if (notifyword2.equals("CallConnect"))
    {
        // call was just connected
    }
    else if (notifyword2.equals("CallDisconnect"))
    {
        // call was just disconnected
    }
    else if (notifyword1.equals("CHAT"))
    {
        // we received an incoming chat message (parse the other parameters to get the sender name and the text to
be displayed)
    }
    else if(notifyword1.equals("ERROR"))
    {
        // we received an error notification; at least log it somewhere
        Log.e("AJVOIP", "ERROR," + notifywordcontent);
    }
    else if(notifyword1.equals("WARNING"))
    {
        // we received a warning notification; at least log it somewhere
        Log.w("AJVOIP", "WARNING," + notifywordcontent);
    }
    else if(notifyword1.equals("EVENT"))
    {
        // display important event for the user
        Log.v(notifywordcontent);
    }
}
}
}

```

## Parameters

The Android SDK is very flexible and you have a long list of parameters that you can use, however this doesn't mean that the usage is difficult. You can ignore most of these them and use only those few relevant for your needs also outlined in the usage example. Usually you only have to pass the basic parameters and change the advanced parameters only if really required for you specific use-case.

Parameters can be specified with the SetParameter or SetParameters API calls.

All parameters can be passed as strings and will be converted to the proper type internally by the Android SIP library .

Note:

- Once a parameter is set, it might be cached by AJVoIP and used even if you remove it later. To prevent this, always set all the parameters to their value if you changed it before. Strings can be set to "DEF" or "NULL". So instead of just deleting, set its value to "DEF" or "NULL". "DEF" means that it will use the parameter default value if any. "NULL" means empty for strings, otherwise the parameter default value. Example: `transport=DEF`
- Not all parameters can be changed at runtime. It is recommended to set all the relevant parameters (with the SetParameter or SetParameters functions) before to call the Start function. You can just restart the sip stack if you need reconfiguration at runtime (stop the current AJVoIP instance and create a new one).

## Basic Parameters

These are the most important parameters.



## **serveraddress**

(string)

The domain name or IP address of your SIP server. By default it uses the standard SIP port (5060). If you need to connect to other port, you can append the port after the address separated by colon.

Examples:

"mydomain.com" -this will use the default SIP port: 5060  
"sip.mydomain.com:5062"  
"10.20.30.40:5065"

Default value is empty.

*If not set, then you (or the users) will be able to call only using full SIP URI and it is more difficult to accept incoming calls. If set, then any username/phone number can be called what is accepted by the server.*

*As the SIP server you can use any softswitch, IP-PBX, SIP proxy server or SIP gateway (with or without registration). Some SIP services requires the use of an [outbound proxy](#).*

## **username**

(string)

This is the SIP username (A number/Caller-ID for the outgoing calls). The AJVoIP SIP endpoint will authenticate with this username on your SIP server.

When compact is true, then this parameter must be filled properly. Otherwise it can be empty or omitted so the users will have to type it.

Default value is empty.

*Note: If you need a different name for SIP user name and Auth name (authorization name) then you can use the [sipusername](#) parameter.*

## **password**

(string)

SIP authentication password.

If your server doesn't require digest authentication or if you need only peer to peer calls then this parameter can be omitted.

Default value is empty.

## **Advanced Parameters**

*These parameters are more rarely used and should be set only if you have a specific need or a good VoIP/Android knowledge. You should modify only those parameters which you fully understand, otherwise better if you leave all with the default values (the default values are already optimized for production).*

## **sipusername**

(string)

Specify default SIP username. Otherwise the "username" parameter will be used for both the username and the authentication name.

If this is not specified, then the "username" will be used for the From field and also for the authentication.

If both username and sipusername is set then

-the username will be used in the From and Contact fields (CLI/caller-id)

-the sipusername will be used for authentication only

Default is empty.

## **displayname**

(string)

Specify default display name used in "from" and "contact" headers (Enduser full name).

Default is empty (the "username" field will be displayed for the peers)

## **transport**

(int)

Transport protocol for the SIP signaling

-1: auto (auto guess)

0: UDP (User Datagram Protocol. The most commonly used transport for SIP)

1: TCP (signaling via TCP. RTP will remain on UDP)

2: TLS (encrypted signaling)

3: HTTP tunneling (both signaling and media. Supported only by mizu server or mizu tunnel)

4: HTTP proxy connect (requires tunnel server)

5: Auto (automatic failover from UDP to HTTP if needed)

Default is -1.

*Note:*

*To enable full encryption set both the transport and the mediaencryption parameter to 2.*

*If you set TLS (2), then make sure that you are using the correct [serveraddress](#) parameter. SIP servers usually listens for TLS on port 5061, thus the serveraddress should look like yourdomain:5061.*

*If the SIP port is configured to 5061 and the transport parameter is not set, then it might default to 2 (TLS).*

---

## mediaencryption

(int)

Media encryption method (encryption for the RTP streams)

-1: auto (will try SRTP if transport is TLS)

0: not encrypted (default)

1: auto (will encrypt if initiated by other party)

2: SRTP

3: ZRTP (experimental)

Default is -1.

*Note: To enable full encryption set both the transport and the mediaencryption parameter to 2.*

---

## strictsrtp

(int)

Media encryption method

0: most compatible

1: default auto

2: strict (might disconnect if peer is not respect the standard or on protocol error)

3: allow only strict SRTP call, otherwise disconnect

Default: 1

---

## proxyaddress

(string)

Outbound proxy address (Examples: mydomain.com, mydomain.com:5065, 10.20.30.40:5065)

Leave it empty if you don't have a stateless proxy. (Use only the serveraddress parameter)

Default value is empty.

---

## md5

(string)

Instead of using the password parameter you can pass an MD5 checksum for better protection: MD5(username:realm:password)

*(The parameters are separated with the ':' character)*

*The realm is usually your server domain name or IP address (otherwise it is set on your server)*

*If you are not sure, you can find out the realm in the "Authenticate" headers sent by your server with the "401 Unauthorized" messages. Example:*

*WWW-Authenticate: Digest realm="YOURREALM", nonce="xxx", stale=FALSE, algorithm=MD5*

Default is empty.

---

## realm

(string)

Set if your server realm (SIP domain) is not the same with the "serveraddress" parameter.

If the "md5" parameter was set, then this must match with the realm used to calculate the md5 checksum.

Default is empty, which means that the "serveraddress" will be used.

---

## register

(int)

With this parameter you can set whether the SIP UA should register (connect) to the sip server.

0: no

1: auto guess (yes if username/password is set, otherwise no)

2: yes

AJVoIP will also reregister automatically based on the “registerinterval” parameter.  
Default value is 1.

## registerinterval

(int)  
Registration interval in **seconds** (used by the re-registration expires timer).  
Default value is -1 (auto guess)

Valid range is -1 (auto) or between 10 and 30000.

Notes:

- Many servers will not accept values above 3600 (although the SIP stack can be auto adjust it based on server negotiation)
- The actual resend of the REGISTER messages might be done at a shorter interval to cover any potential packet loss and network/server delays.
- When set to auto guess (-1), it will calculate an optimal interval depending on the circumstances such as network type, server load, transport method, data saver settings and others. It will result to around 90-180 under normal conditions on UDP or 600 on TCP.
- If your softswitch supports keep-alive messages (to prevent NAT binding timeouts), then you might set to a longer interval (~3600 sec) to prevent high CPU usage on your server especially if you have many hundreds of SIP UA running at the same time. If your server doesn't support keep-alive, then you might set this to a lower value (between 30 and 90 sec. 60 sec is a good choice for most NAT devices and routers). Note that usually this is not necessary because server side support is not needed to keep the NAT bindings.
- If the register expire interval is not accepted by the server, then the SIP stack is capable to automatically negotiate a new value as directed by the server Min-Expire header or auto-guess.
- The register expires might be auto set to a higher value if push notifications are enabled to reduce the need of push re-register/rebind requests.

## needunregister

(boolean)  
Set to false to prevent unregister messages to be sent by AJVoIP (for example to prevent unregister on web page reload).  
Default is true

## extraregisteraccounts

(boolean)  
Use this setting for multi-account registration.  
You can specify multiple SIP accounts in the following format:  
IP,usr,pwd,t,proxy,realm,authuser;IP2,usr2,pwd2;IP3,usr3,pwd3, , ,realm3;IP4,usr4,pwd4...  
where:

- IP: is the SIP server address (domain or IP:port)
- usr: is the SIP username
- pwd: is the SIP password
- t: is the register timeout in seconds (optional)
- proxy: SIP proxy (optional)
- realm: SIP realm (optional)
- authusr: auth (sipusername if separate extension id and authorization username have to be used)

See the [Multiple account registration](#) FAQ for more details.

## acceptsrvexpire

(int)  
Accept the expires interval sent by the server.  
0: no  
1: yes (prioritize the contact expire)  
2: yes (prioritize the global expire)  
Default value is 1.

## keepaliveival

(int)  
NAT keep-alive packet send interval in milliseconds.  
Keep-alive is a mechanism to keep the NAT open between register resends (so the server can initiate a new incoming transaction on the same stream with no issues, such as incoming call).

Possible values:

- -1: auto (will default to around 28000 -28 sec- on UDP and 600000 – 10 min- on TCP)
- 0: disabled
- other: interval in milliseconds (must be above 3000, otherwise treated as seconds)

Default value is -1.

---

### *keepalivetype*

(int)

NAT keep-alive packet type.

0=no keep-alive

1=space + CRLF (\r\n) (very efficient because low bandwidth and low server usage)

2=NOTIFY (standard method)

3=CRLF (\r\n) (very efficient because low bandwidth and low server usage. Not recommended)

4=CRLFCRLF (\r\n\r\n) (very efficient because low bandwidth and low server usage. After RFC draft)

Default is 4.

---

### *autocall*

(boolean)

If set to true then the Android SIP library will immediately starts the call with the given parameters (for example with your page load). The serveraddress, username, password, callto must be also set for this to work.

Default value is false.

---

### *callto*

(string)

Can be any phone number/username that can be accepted by your server or a SIP URI. Used with “autocall” to specify the destination number.

Default value is empty.

---

### *use\_rport*

(int)

Check rport in SIP signaling (requested and received from the SIP server by the VIA header)

0=don't ask (rtport request will not be added to the VIA header)

1=use only for symmetric NAT (only when it is sure that the public address will be correct)

2=always (always request and use the returned value except if already on public ip)

3=request even on public IP (meaningless in most cases)

9=request with the signaling, but don't use the returned value (good if you want to keep the local IP and for peer to peer calls)

Change to 0 or 2 only if you have NAT issues (depending on your server type and settings)

(You might adjust also the use\_fast\_stun parameter if you change the use\_rport)

Default is 1

---

### *upnpnat*

(int)

Nat traversal via UpNP supported routers.

0: disable

1: enable

Default is 1

---

### *use\_fast\_ice*

(int)

Fast ICE negotiations (for p2p rtp routing):

0=no (set to 0 only if your server needs to always route the media)

1=auto

2=yes

3=always (not recommended)

Default is 1

Note: if set to 1 or 2 then the stun should not be disabled

---

### *use\_fast\_stun*

(int)

Fast stun request on startup.

-1=force private address (if the client has both private and public IP, than the private IP will be sent in the signaling)

0=no  
1=use only for stable symmetric NAT  
2=use only if both tests match even if not symmetric (recommended)  
3=use for symmetric NAT even if only one match  
4=always  
5=use even on public IP  
Change if you have NAT issues (depending on your server type and settings)  
(You might adjust also the use\_rport parameter if use\_fast\_stun is changed)  
Default is 2

---

### *udpconnect*

(int)  
Specify whether the UDP have to be connected before sending on the socket. (Some IP-PBX might require udp connect and in this way the Android SIP library can always detect its local address correctly. However this should not be used whit multiple servers or separate domain and outbound proxy)  
0=no  
1=on init  
2=on first send (not recommended. can block)  
3=on both or any (not recommended)  
Default value: 0

---

### *changesptoring*

(int)  
If to treat session progress (183) responses as ringing (180). This is useful because some IP-PBX never sends the ringing message, only a session progress and might start to send in-band ringing (or some announcement)  
The following values are defined:  
0: do nothing,  
1: change status to ring  
2: start local ring and be ready to accept media (which is usually a ringtone or announcement)  
3: start media receive and playback (and media recording if the “earlymedia” parameter is set)  
4: change status to ringing and start media receive and playback (and media recording if the “earlymedia” parameter is set to true)  
Default value is 2.

\*Note: on ringing status AJoVoIP is able to generate local ringtone. However this locally generated ringtone playback is stopped immediately when media is started to be received from the server (allowing the user to hear the server ringback tone or announcements)

---

### *allowcallredirect*

(int)  
Set to 1 to auto-redial on 301/302 call forward.  
Set to 0 to disable auto call forward.  
Default value is 1.

---

### *natopenpackets*

(int)  
Change this option only if you have RTP setup issues with your server(s).  
UDP packets to send to open the NAT device and initiate the RTP. Some servers will require at least 5 packets before starting to send the media after the 183 “session in progress” response. In this case set this value to 10 (In this way the server will receive at least 5 packets even on high packet loss networks)  
0: no  
1: write only an empty udp packet  
2: write a normal RTP packet  
3 or more: write this number of RTP packets  
  
Default is 2

\*Note: instead of sending more “fake” packets, you can set the “earlymedia” to 1 or more to begin the rtp stream immediately.

\*Note: you can use the “natopenpackettype” to specify the format. 1 means short CRLF packet (default). 2 means full RTP packet with zeroed content.

---

### *earlymedia*

(int)  
Start to send media when session progress is received.  
0: no

1: reserved  
2: auto (will early open audio if wideband is enabled to check if supported)  
3: just early open the audio  
4: null packets only when sdp received  
5: yes when sdp received  
6: always forced yes  
Default is 2.

\*Note: For the early media to work, AJVoIP has to open the NAT when SDP is received. This can be done by sending a few fake rtp packets or by starting to send the media immediately when session in progress is received. The first method consume less bandwidth, but it is not supported by some softswitch.

---

### *usehttpproxy*

(int)  
Used only for HTTP tunneling with Mizu VoIP servers.  
0: no  
1: same as sip proxy (proxyaddress)  
2: system default  
3: manual (must be set by the httpproxyurl parameter –deprecated after version 3.5)  
4: auto  
Default value is 4.

---

### *httpserveraddress*

(string)  
Useful when the transport parameter is set to 4 (auto) to specify the http tunneling gateway address.  
Default value is null (address loaded from the “serveraddress” parameter)

---

### *dtmfmode*

(int)  
DTMF send method  
0=disabled  
1=SIP INFO method (out-of-band in SIP signaling INFO messages)  
2=auto (auto guess from peer advertised capabilities)  
3=INFO + NTE  
4=NTE (Named Telephone Events as specified in RFC 2833 and RFC 4733)  
5=In-Band (DTMF audio tones in the RTP stream)  
6=INFO + InBand

Default is 2 (and you should change it only if you have a good reason to do so, since the auto-detect should work in all circumstances, except if your SIP server is sending bogus DTMF capabilities).

*Note: When more than one method is used (dtmfmode 3 or 6), the receiver might receive duplicated dtmf digits.*

---

### *sendearlydtmf*

(int)  
Specify whether to allow sending DTMF digits before call connect  
0=no  
1=auto (yes if rfc2833 or inband is allowed and already sent/received rtp packets)  
2=yes (always send)

Default: 1

---

### *voicemail*

(int)  
Subscribe to voicemail notifications (MWI). Accepted values:  
0=disabled  
1=display voicemail only if NOTIFY is received automatically without subscription  
2=auto-detect if voicemail SUBSCRIBE is needed  
3=subscribe for voicemail messages after successful registration  
4=subscribe for voicemail messages on startup  
Default value is 2. Set to 3 if your server has support for MWI to be sure that AJVoIP will check the voicemail.

## voicemailnum

(String)

Specify the voicemail address. Most IP-PBX will automatically send the voicemail access number so you don't need to set this parameter.

## transfertype

(int)

-1=default transfer type (same as 6)

0=call transfer is disabled

1=transfer immediately and disconnect with the A user when the Transf button is pressed and the number entered (unattended transfer)

2=transfer the call only when the second party is disconnected (attended transfer)

3=transfer the call when AJVoIP is disconnected from the second party (attended transfer)

4=transfer the call when any party is disconnected except when the original caller was initiated the disconnect (attended transfer)

5=transfer the call when AJVoIP is disconnected from the second party. Put the caller on hold during the call transfer (standard attended transfer)

6=transfer the call immediately with hold and watch for notifications (unattended transfer)

7=transfer with no hold and no disconnect (simplest unattended transfer)

8=transfer with conference (will put the parties to conference on transfer; will mute or hold the old party by default)

Default is -1 (which is the same as 6)

Note:

- *Unattended means simple immediate transfer (just a REFER message sent)*
- *Attended transfer means that there will be a consultation call first*
- *The most popular transfertypes are 1, 5 and 6*
- *If you have any incompatibility issue, then set to 7 (unattended is the simplest way to transfer a call and all sip server and device should support it correctly)*
- *More details can be found [here](#).*

## transfwithreplace

(int)

Specify if replace should be used with transfer so the old call (dialog) is not disconnected but just replaced.

This way the A party is never disconnected, just the called party is changed. The A party must be able to handle the replace header for this.

-1=auto

0=no

1=yes

Default is -1

## allowreplace

(int)

Allow incoming replace requests.

0=no

1=yes and always disconnect old ep

2=yes and don't disconnect if in transfer

3=yes but never disconnect old ep

Default is 2.

## discontransfer

(int)

Specify if line should disconnect after transfer if not determined by the other transfer related configurations.

-1=auto

0=never

1= on C party connected status

2= on timeout

3= on connected or timeout

4= on ok for refer

Default is -1

## disconincomingrefer

(int)

Specify if line should disconnect after incoming transfer

-1=auto

0=no

1= yes

Default is -1

---

### *transferdelay*

(int)

Milliseconds to wait before sending REFER/INVITE while in transfer.

Default value is 400.

---

### *checksubscriptionstate*

(int)

Specify if to handle transfer subscription state (such as reload the call on transfer failure)

-1=auto

0=no

1= disconnect

2= reload

Default is -1

---

### *subscribefortransfer*

(int)

Create subscribe dialog for call transfer.

-1=auto

0=never

1= if no notify received

2= always

Default is -1

---

### *enabledirectcalls*

(int)

Specify whether to enable direct call to SIP URI (peer to peer or via server)

0=no (so you should use only the username part of the SIP URI to make calls. set the domain part as the sipserveraddress parameter)

1=check IP in URI (will recognize full SIP URI if the domain part can be resolved to a valid IP)

2=always check (so you can make calls to full SIP URI without a SIP server to be set)

3=crossdomain (so you can register to domain A and make direct call to domain B)

Default is 1

---

### *charset*

(string)

Set the character decoding for SIP signaling.

Default is empty (will load the local system default).

More details:

<http://docs.oracle.com/javase/7/docs/api/java/nio/charset/Charset.html>

<http://www.iana.org/assignments/character-sets/character-sets.xhtml>

---

### *checksrvrecords*

(int)

SRV DNS record lookup setting:

-1: auto (will check SRV record for the VoIP server, but remembers if fails and will not check again next time)

0: don't lookup (will use only A record)

1: lookup A record first. If fails then lookup srv record (because mostly the srv record is not set anyway)

2: lookup SRV record first for VoIP server address. If fails then lookup A record (RFC compliant)

3: always lookup SRV record first. If fails then lookup A record

4: check also without the \_sip.\_udp. prefix

If the SRV lookup returns multiple records, than SIP UA will failover to the next server on connection failures.

Default value is -1.

---

### *dnslookup*

(int)



Domain record lookup mode  
0=auto (same as 2)  
1=yes always re-query  
2=use cache if needed (default)  
3=use cache whenever possible  
4=from cache only  
5=disable  
Default value is 0.

---

### ***forcewifi***

(int)  
Force WiFi network.  
Possible values:  
0=no  
1=auto  
2=lock in call  
3=lock always  
4=always  
5=always lock  
6=extra  
Default value: 1

---

### ***keepdeviceawakeincall***

(int)  
Keep device awake during calls.  
Possible values:  
0=no  
1=basic only  
2=auto  
3=full then partial  
4=always full only  
Default value: 2

---

### ***cpupartiallock***

(boolean)  
Keep a partial lock on the CPU while in call to prevent sleep.  
Default value is true.

---

### ***cpualwayspartiallock***

(boolean)  
Always keep a partial lock on the CPU to prevent sleep.  
Default value is false.

---

### ***unlockphone***

(boolean)  
Auto handle keyguard lock.  
Default value is true.

---

### ***proximitysensor***

(int)  
Enable/disable proximity sensor during calls.  
Possible values:  
0=disable  
1=software based (deprecated)  
2=hardware based  
Default value: 2

---

### ***checknativecall***

(int)  
Specify how to handle if there is a native/mobile call in progress.  
Possible values:  
0=don't check (will behave as it would be without native call in progress)  
1=basic behavior changes (such as no ring)  
2=don't alter the audio  
Default value: 1  
(Should be set to 1 if using connection service or keep 1 always)

---

### ***aspeakermode***

(int)  
Speaker device to be used.  
Possible values:  
0=default (usually speakerphone/headphone)  
1=headphone (speakerphone/headphone)  
2=speakerphone (loudspeaker)  
Default value: 0

---

### ***autousebluetooth***

(int)  
Specify when to use Bluetooth device.  
Possible values:  
0=guess  
1=no  
2=yes  
Default value: 0

---

### ***video***

(int)  
Enable/disable video.  
-1: auto (default)  
0: disable  
1: enable  
2: force always

RTC capabilities must be available for video to work.

---

### ***focusaudio***

(int)  
Specify whether to use audio "focus". (Auto decrease the volume of other apps).  
Possible values:  
0=auto  
1=no  
2=yes  
Default value: 0

---

### ***speakerphoneoutput***

(int)  
Speakerphone output device.  
Possible values:  
0: Auto guess  
1: Speaker  
2: Speaker Forced  
3: VoIP  
4: Bluetooth  
5: No changes  
Default value: 0

## ***audiorecorder***

---

(int)  
Audio recorder stream.  
Possible values:  
0: Default  
1: Auto guess  
2: Mic  
3: Voice call  
4: Voice downlink  
5: Voice uplink  
6: Voice communication  
Default value: 1  
(Normally it should be set to 0,1 or 2. Other values are very unusual)

## ***audioplayer***

---

(int)  
Audio player stream for calls.  
Possible values:  
0: STREAM\_VOICE\_CALL  
1: STREAM\_SYSTEM  
2: STREAM\_RING  
3: STREAM\_MUSIC  
4: STREAM\_ALARM  
5: STREAM\_NOTIFICATION  
Default value: 0

## ***speakerphoneplayer***

---

(int)  
Audio speakerphone player stream.  
Possible values:  
0: STREAM\_VOICE\_CALL  
1: STREAM\_SYSTEM  
2: STREAM\_RING  
3: STREAM\_MUSIC  
4: STREAM\_ALARM  
5: STREAM\_NOTIFICATION  
6: default  
Default value: 0

## ***incomingcallalert***

---

(int)  
Audio player stream for ring.  
Possible values:  
0: STREAM\_VOICE\_CALL  
1: STREAM\_SYSTEM  
2: STREAM\_RING  
3: STREAM\_MUSIC  
4: STREAM\_ALARM  
5: STREAM\_NOTIFICATION  
Default value: 2

## ***speakermode***

---

(int)  
Specify when to switch to speaker mode.  
Possible values:  
0: auto  
1: never  
2: always  
Default value: 0

## ***enableaudiostreams***

---

(int)

You can disable audio playback and/or recording streams with this option (will still open the device, but will not record/playback)

0=disable all

1=disable recording

2=disable playback

3=enable all

Default value is 3.

## ***useaudiodevicerecord***

---

(boolean)

Set to false to disable using the audio input device (microphone). In this case you should also set the meditimeout parameter to 0.

Default is true.

## ***useaudiodeviceplayback***

---

(boolean)

Set to false to disable using the audio output device (speaker/earphone). In this case you should also set the meditimeout parameter to 0.

Default is true.

## ***vibrate***

---

(int)

Vibrate on incoming call

0=auto (depends on phone settings)

1=no

2=yes

Default is 0.

## ***playing***

---

(int)

Generate ringtone for incoming and outgoing calls.

0=no (you can generate ringtone also by using the Java API to playback a sound file when you receive ringing notifications)

1=play ringtone for incoming calls

2=play ringtone for incoming and outgoing calls. (ringtone for outgoing calls can be generated also by your VoIP sever. When remote ringtone is received, java softphone will stop the local ringtone playback immediately and starts to play the received ringtone or announcement)

Default is 2.

## ***ringtone***

---

(string)

Specify a ringtone sound file or URI (system ring tones) to be used.

*If you use a file instead of a system ringtone URI:*

- *Set only the file name, not the full path. Copy the file to your app folder or near the AJVoIP library*
- *The file should be in the following format: PCM SIGNED 8000.0 Hz (8 kHz) 16 bit mono (2 bytes/frame) in little-endian (128 kbits).*
- *You can use any sound editor to convert your file to this format (usually from File menu -> Save as).*

Default value is empty. If not specified, then AJVoIP will use the default ringtone for call alert.

### Example:

This example code illustrates how to present the UI for the user for choosing a native ringtone from android device ad how to get the path of the ringtone audio file:

Open ringtone UI:

```
public final int RINGTONE_REQCODE = 123456; // request code used in onActivityResult
String title = "Select your ringtone";

Intent intent = new Intent(RingtoneManager.ACTION_RINGTONE_PICKER);
```

```

intent.putExtra(RingtoneManager.EXTRA_RINGTONE_TITLE, title);
intent.putExtra(RingtoneManager.EXTRA_RINGTONE_SHOW_SILENT, false);
intent.putExtra(RingtoneManager.EXTRA_RINGTONE_SHOW_DEFAULT, true);
intent.putExtra(RingtoneManager.EXTRA_RINGTONE_TYPE, RingtoneManager.TYPE_ALL);
startActivityForResult(intent, RINGTONE_REQCODE);

```

Get the path to the selected ringtone in `onActivityResult`:

```

protected void onActivityResult(int requestCode, int resultCode, Intent data)
{
    if (requestCode == RINGTONE_REQCODE)
    {
        if(resultCode == RESULT_OK)
        {
            String ringTonePath = "";
            Uri uri = data.getParcelableExtra(RingtoneManager.EXTRA_RINGTONE_PICKED_URI);
            if (uri != null)
            {
                // the absolute path to the ringtone audio file selected by the user
                ringTonePath = uri.toString();
                Log.v("AJVOIP", "User selected ringtone path: " + ringTonePath);
                // pass it to AJVoIP
                mysipclient.SetParameter("ringtone", ringTonePath);
            }
        }
        if (resultCode == RESULT_CANCELED)
        {
            Log.v("AJVOIP", "user canceled ringtone selection");
        }
    }
}

```

## ringincall

(int)  
 Ring while in call if incoming or outgoing call  
 0=No  
 1=Only a beep for incoming call  
 2=Yes, normal ring  
 Default value is 1

## checkvolumesettings

(int)  
 Check if audio device is muted or volume settings are too low (and un-mute and/or increase volume if necessary).  
 0: no  
 1: at first run  
 2: always  
 Default value is 1

## volumein

(int)  
 Default microphone volume in percent from 0 to 100. 0 means muted. 100 means maximum volume, 0 is muted.  
 Default is 50% (not changed)

*Note:*  
 The result volume level might be affected by the AGC if it is enabled.  
 Volume levels above 70% might result in distorted sound.  
 Usually it should not be changed as users should control the volume by OS level volume controls.

## volumeout

(int)  
 Default speaker volume in percent from 0 to 100. 0 means muted. 100 means maximum volume, 0 is muted.  
 Default is 50% (not changed)

*Note:*  
*The result volume level might be affected by the AGC if it is enabled.*  
*Volume levels above 70% might result in distorted sound.*  
*Usually it should not be changed as users should control the volume by OS level volume controls.*

## **volumering**

(int)  
Default ringback volume in percent from 0 to 100. 0 means muted. 100 means maximum volume, 0 is muted.  
Default is 50% (not changed)

*Note: Usually it should not be changed as users should control the ringer by OS level volume controls.*

## **beeponconnect**

(int)  
Will play a short sound when calls are connected  
0=Disabled  
1=For auto accepted incoming calls  
2=For incoming calls  
3=For outgoing calls  
4=For all calls  
Default value is 0

## **playdtmfsound**

(int)  
DTMF sounds on key press.  
0=No  
1=Yes for one digit  
2=Yes also if multiple digits  
Default is 1

## **agc**

(int)  
Automatic gain control.  
0=Disabled  
1=For recording only  
2=Both for playback and recording  
3=Guess  
Default value is 3

*This will also change the effect of the volumein and volumeout settings.*

## **plc**

(boolean)  
Enable/disable packet loss concealment  
Default is true (enabled)

## **vad**

(int)  
Enable/disable voice activity detection.  
0: auto  
1: no  
2: yes for player (will help the jitter)  
3: yes for recorder  
4: yes for both  
Default is 2.

#### Notes:

-The vad parameter is automatically set to 4 by default if the aec2 algorithm is used.

-If you wish to use VAD related statistics in your application, you might have to also set the “vadstat” parameter after your needs. Possible values: 0=no,1=auto (default),2=detect no mic audio,3=send statistics. See the VAD notification and VAD for more details.

-If you want to disable audio related notifications (microphone warning on no signal detected) then set the “enablenomicvoicewarning” parameter to 0

### rtpstat

(int)

Enable/disable RTP statistics by triggering [RTPSTAT](#) notifications.

Possible values:

-1: auto (will trigger RTPSTAT events in every 6-7 seconds and more frequently at the beginning of the calls)

0: disabled

Positive value: seconds to generate RTPSTAT events.

Default is 0 (disabled)

More details [here](#).

### aec

(int)

Enable/disable acoustic echo cancellation

0=no

1=yes except if headset usage guessed

2=yes if supported

3=forced yes even if not supported (might result in unexpected errors)

Default is 1.

#### Note:

*The aec decision might be overwritten or modified by the aectype parameter.*

*After tests, the success rate of the built-on AEC algorithms is above 90%. This is considered a good value as there are no any perfect aec algorithms, but it might not work (or partially work) in some devices or circumstances (depends on many factors such as audio hardware, driver, OS/device, environment/room, codec, network delay).*

For more details, read [here](#).

### aectype

(string)

AEC algorithm(s) to use.

One or more of the following strings separated by comma:

- auto: will select automatically based on circumstances (CPU power, device capabilities, network)
- none: disable aec
- software: software aec (requires extra CPU processing)
- hardware: android hardware aec capabilities (not supported on all phones)
- fast: a fast software aec implementation (used preferably on slow/old devices or in addition for the above algorithms)
- volume: this will just decrease the volume when speech detected from other end (using VAD)

Default is auto.

#### Note:

- *It is recommended to leave both the aec and aectype values with its default values*
- *To force all echo cancellations algorithms you might set the aec to “2” and the aectype to “software,hardware,fast,volume” (this might be too much, forcing the software to do unnecessary processing and in some circumstances it might remove too much audio)*

For more details, read [here](#).

### denoise

(int)

Noise suppression.

0=Disabled

1=For recording only

2=Both for playback and recording

3=Auto guess

Default value is 3

## ***silencesuppress***

(int)  
Enable/disable silence suppression  
Usually not recommended unless your bandwidth is really bad and expensive.  
-1=auto  
0=no (disabled)  
1=yes  
Default is -1 (which means no, except mobile devices with low bandwidth)

## ***hardwaremedia***

(int)  
Enable the usage of OS/hardware level audio processing for aec/denoise/silence suppress.  
0=auto  
1=no  
2=yes  
Default is 0

*Note: even if this is set to 2, the media stack might not use the android hardware capabilities if you disable aec/denoise/silencesuppress by their respective parameters*

## ***rtcp***

(boolean)  
Enable/disable rtcp. (RFC 3550. Partial support)

## ***codec***

(string)  
List of allowed audio codec's separated by comma.  
Will accept one or more of the following strings (upper or lower case doesn't matter):  
pcmu, pcma, g711 (for both PCMU and PCMA), g719, gsm, ilbc, speex, speexwb, speexuwb, opus, opuswb, opusuwb, opusswb, def

By default the Android SIP library will automatically choose the best codec depending on available codec's, circumstances (network/device) and peer capabilities.  
Set this parameter only if you have some special requirements such as forcing a specific codec, regardless of the circumstances.  
Default: empty (which means auto detection and negotiation)  
Recommended value: leave it empty for "best" codec negotiation unless if you have some specific requirement.

Example: **OpusWB,G.729,PCMU** (This will disable Speex, GSM, iLBC, GSM and PCMA).

You can also set one single codec (if your server/peers allows only one codec or for testing to rule out all kind of codec negotiation related issues).

You can set to "**def**" to enable all the default codec's again.

*Under normal circumstances, the following is the built-in codec priority:*

- I. Wideband Speex and Opus (These are set with top priority as they have the best quality. Likely used for VoIP to VoIP calls if the peer also has support for wideband)
- II. G.729 (Usually the preferred codec for VoIP trunks used for mobile/landline calls because it's excellent compression/quality ratio for narrowband)
- III. iLBC, GSM (If G.729 is not supported then these are good alternatives. iLBC has better characteristics and GSM is better supported by legacy hardware)
- IV. G.711: PCMU and PCMA (Requires more bandwidth, but has the best narrowband quality)

*The default codec order will highly depends on the device CPU power (high-complexity codec's are deprioritized on low-end devices) and network type (high bandwidth codec's are deprioritized on slow networks such as GPRS, 2G or slow 3G). On a decent device with good internet connection (WiFi, LTE, 5G, 4G or good 3G) the softphone should pick up the Opus wideband if peer has support for this codec. If peer has support only for narrowband then G.729 should be selected, otherwise another codec negotiated with the peer endpoint.*

More details [here](#).

Note: for the codec configuration, either use the codec/prefcodec settings OR the use\_xxx settings (where xxx is the codec name; listed below).  
You can achieve similar result with both. The use\_xxx settings are a little bit more flexible regarding the codec prioritization.

## ***prefcodec***



(int)

Set your preferred audio codec.

Will accept one the following strings (upper or lower case doesn't matter):

pcmu, pcma, g711 (for both PCMU and PCMA), g719, gsm, ilbc, speex, speexwb, speexuwb, opus, opuswb, opusuwb, opusswb

Default is empty which means the built-in optimal [prioritization](#).

By default the SIP stack will present the codec list optimized regarding the circumstances (the combination of the followings):

- available client codec set (not all engines supports all codecs)
- server codec list (depending on your server, peer device or carrier)
- internal/external call: for IP to IP calls will prioritize wideband codecs if possible, while for outbound calls usually G.729 will be selected if available
- network quality (bandwidth, delay, packet-loss, jitter): for example iLBC is more tolerant to network problems if supported
- device CPU: some old mobile devices might not be able to handle high-complexity codec's such as opus or G.729. G711 and GSM has low computational costs

You can also fine-tune the codec settings with the use\_XXX settings described below.

## ***vcodemc***

(string)

List of allowed video codec's separated by comma (H264, VP8, VP9).

You might use this parameter to exclude some codec from the offer list.

For example if you wish to use only H.364, then set this to: **"H264"**

Default: empty (which means auto detection and negotiation)

## ***video\_bandwidth***

(int)

Max bandwidth for video in kbits.

It will be sent also with SDP "b:AS" attribute.

Default is 0 which means auto negotiated via RTCP and congestion control.

## ***video size parameters***

(int)

You can suggest the size of the video (in pixels) with the following parameters:

- video\_width
- video\_height
- video\_min\_width
- video\_min\_height
- video\_max\_width
- video\_max\_height

## ***use\_gsm***

(int)

GSM codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1.

## ***use\_ilbc***

(int)

iLBC codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1.

## ***use\_speex***

(int)

Narrowband speex codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1

## ***use\_speexwb***

(int)

Wideband speex codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 2

---

### ***use\_speexuwb***

(int)

Ultra wideband speex codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1

---

### ***use\_opus***

(int)

Narrowband (8000 Hz) opus codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1

---

### ***use\_opuswb***

(int)

Wideband (16000 Hz) opus codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 2

---

### ***use\_opusswb***

(int)

Super wideband (24000 Hz) opus codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1

*Note: this codec might not work on all devices, depending on the audio device and driver capabilities!*

---

### ***use\_opusuwb***

(int)

Ultra wideband (fullband at 48000 Hz) opus codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 1

---

### ***use\_g729***

(int)

G.729 codec setting. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 2

*\*In some countries a license/patent is required if you use G.729 so enable only if you have licenses or licenses are not required in your case (consult your lawyer if you are not sure)*

---

### ***use\_pcma***

(int)

G711alaw codec. 0=never,1=don't offer,2=yes with low priority,3=yes with high priority

Default is 2

---

### ***use\_pcmu***

(int)

G711ulaw codec. 0=never, 1=don't offer, 2=yes with low priority, 3=yes with high priority

Default is 1

---

### ***disablewbforpstn***

(int)

This setting will disable speex and opus wideband and ultrawideband for outgoing calls to regular phone numbers since these are usually not supported for pstn calls and they might requires longer initialization.

0: no

1: check at first call

2: check all calls

Default is 0.

## setfinalcodec

---

(int)

Some server cannot handle the final codec offer in the ACK message correctly.

In this case you will have to set this setting to 0, otherwise you will have one way audio.

0=never (RFC compliant)

1=auto guess (not send in case of certain servers and autocorrect in subsequent calls)

2=when multiple codecs are received

3=always reply with the final codec in the ACK message

Default value is 1.

## ims3gpp

---

(int)

Enable [3GPP](#) (IMS/5G/VoLTE) features.

Possible values:

-1: auto detect (default)

0: disable

1: basic

2: full/all

It is also possible to enable only certain [3GPP features](#). In this case use the following parameters instead of `ims3gpp`:

- `ims3gpp_phonenum`: use tel URI and set user=phone (-1: auto, 0: no, 1: user=phone, 2: also tel uri). Note: you might also use the `sipproto` param.
- `ims3gpp_minphonelen`: tel uri only if phone number is longer then this. Default is 4. Set to 0 to use tel also for non-phone number peers
- `ims3gpp_authname`: auth username must contain the domain (-1: auto, 0: no, 1: yes)
- `ims3gpp_ussd`: IMS [USSD](#) described at [3GPP TS 24.390](#). Send with [SendUSSD](#), receive as [USSD](#) notifications (-1: auto, 0: no, 1: yes)
- `ims3gpp_sms`: [+g.3gpp.smsip](#) with MESSAGE using binary encoded [PDU](#)'s described in [3GPP TS 24.011](#) (-1: auto, 0: no, 1: yes)
- `ims3gpp_smsc`: SMSC Center Address number. Otherwise AJVoIP will use the destination number (if that is a phone number)

## enable\_3pcc

---

(int)

Specify if to enable 3PCC Third Party Call Control as described at [RFC 3725](#).

*Note: 3PCC has nothing to do with 3GPP. They are completely different technologies.*

This feature is often used in callcenters or for click-to-call to setup calls between two or more other parties.

Possible values:

0: disable (block 3PCC requests)

1: don't handle

2: accept (handle incoming requests)

3: initiate 3PCC calls by sending with no SDP

4: initiate 3PCC calls by sending SDP with connect IP set 0.0.0.0

5: initiate 3PCC calls by sending SDP with no media line

Default is 2.

If 3pcc is enabled, then AJVoIP will send the codec answer in ACK if not received by INVITE or it will re-INVITE if received SDP with no media line or with 0.0.0.0 contact IP, thus allowing all the possible third party call controls.

Some more related information can be found [here](#), [here](#), [here](#) and [here](#).

You might also set the `autoaccept` parameter to `true` if AJVoIP acts as an auto-responder.

## ed137

---

(int)

Enable/disable the ED-137 behavior to be used for air traffic management services.

Set to 0 to ignore the ED-137 specification (act as normally)

Set to 1 to turn on the ED-137. This will change a list of internal settings and behaviors to conform with the ED-137 specification.

Default value is 0.

See the [ED-137 guide](#) for more details.

## alwaysallowlowcodec

---

(int)

Set to 2 to always put low computational and low bandwidth codec in the offer list, specifically GSM and PCMU. Low CPU or bandwidth devices might choose these codecs (such as a mobile phone on 3G).

Set to 0 to disable.

Default is 1 (auto)

## ***codecframecount***

(int)

Number of payloads in one UDP packet.

By default it is set to 0 which means 2 frames for G729 and 1 frame for all other codec.

## ***udptos***

(int)

Sets traffic class or type-of-service octet in the IP header for packets sent from UDP socket which can be used to fine-tune the QoS in your network. As the underlying network implementation may ignore this value applications should consider it a hint.

The value must be between 0 and 255.

Valid values:

- 0: disabled
- 1: automatic (set to 10 under normal conditions and disabled when in tunneling)
- 2: low-cost routing
- 4: reliable routing
- 8: throughput optimized routing
- 10: low-delay routing
- or'ing the above values (from above 2)

Default value is 1.

Notes:

for Internet Protocol v4 the value consists of an number with precedence and TOS fields as detailed in RFC 1349. The TOS field is bitset created by bitwise-or'ing values such the following :

```
IP_TOS_LOWCOST: 2
IP_TOS_RELIABILITY: 4
IP_TOS_THROUGHPUT: 8
IP_TOS_LOWDELAY: 16
```

The last low order bit is always ignored as this corresponds to the MBZ (must be zero) bit.

For Internet Protocol v6 tc is the value that would be placed into the sin6\_flowinfo field of the IP header.

This parameter might work only in preset environments; the Java SDK might not have enough rights to modify the IP headers.

## ***automute***

(int)

Specify if other lines will be muted on new call

0=no (default)

1=on incoming call

2=on outgoing call

3=on incoming and outgoing calls

4=on other line button click

Default is 0

## ***autohold***

(int)

Specify if other lines will be put on hold on new call

0=no (default)

1=on incoming call

2=on outgoing call

3=on incoming and outgoing calls

4=on other line button click

Default is 0

## ***holdontransfer***

(int)

Specify if line should disconnect after transfer

-1=auto

0=no

1= yes

2= hold and reload if needed

Default is -1

### ***holdtypeonhold***

---

(int)

Specify call hold type.

Call hold is usually initiated by the [Hold](#) function and with parameter you can specify which type of call hold do you wish to request.

Possible values:

-2: no

-1: auto (defaults to 2)

0: no (don't hold. a=sendrecv)

1: reserved (not used)

2: hold: instructs the peer to not send audio (mute speaker. Local JVoIP: a=sendonly, peer: a=recvonly)

3: hold: not sending audio to the other (mute microphone. Local JVoIP: a=recvonly, peer: a=sendonly)

4: hold: both (mute both in/out audio. a=inactive)

Default is -1.

*Note:*

*By default the hold will check the previous state. For example if previously it was local hold (2) and you switch to remote hold (3) then actually will switch o both hold.*

*There is also a **holdexplicit** parameter which if set to 1, then the hold will be done strictly after the holdtypeonhold parameter, without considering previous state. This way you can also change between local and remote hold without the need to unhold first.*

### ***defmute***

---

(int)

Default mute direction

0: both

1: mute out (speakers)

2: mute in (microphone)

3: both

4: both

5: disable mute

### ***ackforauthrequest***

---

(int)

If to send ACK for authentication requests (401,407).

0=no

1=yes (default)

Should be changed only if you have compatibility issues with the server used.

### ***favorizecontactaddr***

---

(int)

You may change it if you have compatibility issues with stateless proxies

0=never

1=no

2= conform RFC

3= yes. Sending for both server and contact URI (default)

4=always

### ***prack***

---

(boolean)

Enable 100rel (PRACK)

Set to false if you have incompatibility issues.

Default is false.

### ***sendmac***

---

(boolean)

Will send the client MAC address with all signaling message in the X-MAC header parameter.  
Default value is false.

*Note: The SDK might not have enough rights to read the MAC address.*

---

### ***useragent***

(string)  
This will overwrite the default User-Agent setting.  
Do not set this when used with mizu VoIP servers because the server detects extra capabilities by reading this header.  
Default is empty.

---

### ***sendsessionid***

(int)  
Specify if to send the Session-ID header as specified in RFC 7989.  
Possible values:  
-1: if received (default)  
0: no (disable)  
1: yes (enable)  
Default is -1.

---

### ***customsipheader***

(string)  
Set a custom sip header (a line in the SIP signaling) that will be sent with all messages. Can be used for various integration purposes (for example for sending the http session id). You can also change this parameter runtime with the SetSIPHeader function.  
Default value is empty.

---

### ***sip\_uui***

(string)  
Specify UUI data (User-to-User Call Control Information as described in RFC 7433).  
Can be used to send data to other endpoints. Not all endpoints and SIP servers supports this feature.  
*If prefixed with \*0: then the UUI will be sent only to peer with the User-to-User header.*  
*If prefixed with \*1: then the UUI will be sent only to target party with call transfer or redirect escaped in Contact or Refer-To URI.*  
*If not prefixed or prefixed with \*2: the UUI will be sent both way.*

Example:

It can be set also at runtime with the SetUUI function.  
Default value is empty.

Simple example: **mydata**  
Example with parameters: **\*2:mydata;encoding=hex;purpose=foo;content=bar**

---

### ***techprefix***

(string)  
Add any prefix for the called numbers.  
Default is empty.

---

### ***normalizenumber***

(int)  
Normalize (called) numbers by removing .-;()[ ]: and space if the string otherwise doesn't contains a-z or A-Z characters (looks like a phone number).  
Possible values:  
-1: auto (usually defaults to 1 yes, except if self username also contains special characters)  
0: no  
1: yes  
Default is -1.

## **honordatasaver**

---

(int)

Take in consideration Android OS Data Saver settings.

0: no

1: yes

Default is 1.

If 1, then it will change a few internal settings to use less data such as longer keep-alive and reregister interval, prioritizing codec's which requires less bandwidth, auto enable silence suppression and more.

## **honordnd**

---

(int)

Take in consideration Android DND settings (Do Not Disturb).

0: no

1: yes

Default is 1.

## **honoraairplan**

---

(int)

Take in consideration Android OS Airplane mode settings.

0: no

1: yes

Default is 1.

If 1, then it will not force network (and wifi) reconnect if no network.

## **mustconnect**

---

(boolean)

If set to true, than users must register before to make any calls.

Default value is false.

## **rejectonphonebusy**

---

(int)

Set to true to reject all incoming call if there is already a native phone call in progress (GSM/mobile call).

Requires READ\_PHONE\_STATE permission.

Possible values:

0: Reject calls

1: Allow calls

2: Forward calls

Default value is 1.

## **rejectonbusy**

---

(boolean)

Set to true to reject all incoming call if there is already a call in progress.

Default value is false.

## **callforwardonbusy**

---

(String)

Specify a number where calls should be forwarded when the user is already in a call. (Otherwise the new call alert will be displayed for the user or a message will be sent on the API)

Default is empty.

## **callforwardalways**

---

(String)

Specify a number where ALL calls should be forwarded.

Default is empty.

## ***calltransferalways***

---

(String)

Specify a number where ALL calls should be transferred.

*This might be used if your softswitch doesn't support call forward (302 answers).*

Default is empty.

## ***autoignore***

---

(int)

Set to ignore all incoming calls.

0=don't ignore

1=silently ignore

2=reject

Default value is 0.

## ***autoaccept***

---

(boolean)

Set to true to automatically accept all incoming calls (auto answer).

Default value is false.

*Note: Autoanswer can be also forced from the server by the "P-Auto-Answer: normal" SIP header.*

## ***blacklist***

---

(string)

Block incoming communication from these users. (users/numbers separated by comma).

Default value is empty.

## ***rejectcallto***

---

(int)

Set to ignore calls if target doesn't match

0=accept all incoming calls

1=check if target user match

2=check rinstance

3=check rinstance strict

4=check all strict

Default value is 0.

## ***hideautocall***

---

(int)

Set to 1 to suppress notifications (STATUS, CDR) from automatically handled calls (ignored, forwarded, rejected and similar).

0=send status notifications also about auto handled calls

1=do not send status notifications from auto handled calls

Default is 0.

## ***ringtimeout***

---

(int)

Maximum ring time allowed in millisecond.

Default is 90000 (90 second)

## ***calltimeout***

---

(int)

Maximum speech time allowed in millisecond.

Default is 10800000 (3 hours)

## ***startsipstack***

---

(int)

Automatically start the sipstack after a specified time.



0=no (the sipstack will be started on the first register or call event)  
1=on startup if not tunneling or serveraddress/username/password are set (the sipstack will be started at app init)  
2=on startup always (the sipstack will be started at app init)  
Other=seconds (the sipstack will be started after the specified seconds)  
Default value is 1

You can set to 0 if there is less change that AJVoIP will be used once the users will open the webpage hosting AJVoIP.  
You can set to 1 or higher if there is a high probability that the user will use AJVoIP to make calls (this will shorten the setup time for the first call)

---

### *timer*

(int)  
You can slow down or speed up the SIP protocol timers with this setting. You may set it to 15 if you have a slow server or slow network.  
Default value is 10.

---

### *timer2*

(int)  
Same as “timer” but it affects idle, connect and ring timeout and maximum call durations.  
Default value is 10.

---

### *mediatimeout*

(int)  
RTP timeout in seconds to protect again dead sessions.  
Calls will be disconnected if no media packet is sent and received for this interval.  
You might increase the value if you expect long call hold or one way audio periods.  
Set to 0 to disable call cut off on no media.  
Default value is 300 (5 minute)

---

### *mediatimeout\_notify*

(int)  
RTP timeout in seconds for API notify.  
After this timeout a warning message is sent via notifications without any further action.  
The following log will be generated: “WARNING,media timeout (notify)”  
Default value is 0 (disabled)

---

### *rtpkeepaliveival*

(int)  
RTP stream keep-alive packet send interval in milliseconds.  
This is useful if your PBX has an RTP timeout setting to prevent disconnects when the java softphone is hold or muted.  
Default value is 0. (You might set it to 25000 for example)

---

### *sendrtponmuted*

(boolean)  
Send rtp even if muted (zeroed packets)  
Set to true only if your SIP server is malfunctioning when no RTP is received.  
Default value is false.

---

### *discmode*

(int)  
For call disconnect compatibility improvements. Some VoIP devices might have bugs with CANCEL forking, so it is better to always send a BYE after the CANCEL message on call disconnect. In this case set the discmode parameter to 3.  
1: quick  
2: conform the RFC  
3: send BYE after CANCEL when needed  
4: double: always repeat the CANCEL and the BYE messages  
Default value is 2.

---

### *waitforunregister*

(int)

Maximum time in milliseconds to wait for unregistration when the Unregister is called or the java sip stack is closed.

If set to 0 that an unregister message is sent (REGISTER with Expires set to 0) but AJVoIP is not waiting for the response, which means that it will not repeat the un-register in case if the UDP packet was lost.

Default value is 2000.

---

### ***detectlanpeers***

(int)

Auto detect other SIP endpoints on the same LAN (broadcast message) such as colleagues at the network place or family members behind the home wifi.

When other user is found, a NEWUSER event notification is triggered.

Possible values:

0: no (will disable also the listener so other endpoints will not be able to detect it)

1: listen only (will be discoverable)

2: yes find others

Default is 2.

---

### ***textmessaging***

(int)

Specify text messaging mode (IM/chat/SMS/API)

-1: auto guess or ask (default)

0: disable all

1: disable incoming messages and auto guess outgoing mode

2: disable message sending and auto guess incoming mode

3: reserved (you might implement HTTP API based chat for this externally)

4: reserved (you might implement native SMS for this externally)

5: VoIP SMS

6: VoIP IM/chat (SIP MESSAGE)

Set the [ims3gpp\\_sms](#) parameter to 1 or 2 to use 3GPP binary encoded messages for SIP MESSAGE or to 0 to always disable.

*Note: the old haschat and chatsms parameters are deprecated now but still supported*

---

### ***offlinechat***

Will try to resend not delivered messages later (on next register and/or when any message received from peer). The offline message queuing will take care of filtering out duplicates and will try to resend the message multiple times on failure until max number of resend or timeout reached.

(int)

-1=auto (usually yes, no for 3gpp sms)

0=no (disable offline chat)

1=yes (default)

2=force always

Default is -1.

---

### ***encrypted***

(boolean)

Specify if the transport will be encrypted (both media and the signaling)

Compatible only with Mizu VoIP servers.

Automatically turned on when using http tunneling.

For standard encryption you can use TLS/SRTP with the transport/mediaencryption parameters.

Default is false.

---

### ***authtype***

(int)

Some IP-PBX doesn't allow "web" or "proxy" authentication.

0=normal

1=only proxy auth

2=only simple auth

---

### ***pwdencrypted***

(int)  
Specify if you will supply encrypted passwords via parameters or via the Java API  
0=no (default)  
1=xor  
2=des+base64  
3=xor+base64 (this is the preferred method; easiest but still secure enough)  
4= base64  
This method is deprecated from version 3.4. All parameters can be passed encrypted now by just prefixing them with the “encrypted\_\_X\_\_” string where X means the id of the encryption method used.

From version 4.8 there is no need to specify this parameter anymore. Just prefix any parameter with encrypted\_X as described [here](#).

---

### **voicerecording**

(int)  
0=no (default)  
1=local (in the user home directory)  
2=remote ftp or http upload  
3=both

---

### **voicerecfilename**

(int)  
The format of the recorded filenames.  
0=date-time + peer name (default)  
1=date-time + sip call-id  
2=sip call-id  
3=date-time + username  
4=date-time + username + peer name

The date-time will be formatted in the following way: yyyyMMddhhmmss

*Note: You can also use the “voicerecfilenameprefix” parameter to add a prefix for the file name.*

---

### **voicerecftp\_addr**

(string)  
FTP location for the recorded voice files if the “voicerecording” parameter is set to 2 or 3.  
Format: <ftp://USER:PASS@HOST:PORT/PATH/TO/THEFILE>  
Example: <ftp://user01:pass1234@ftp.foo.com/FILENAME>

The FILENAME part of the string will be replaced with the file name according to the “voicerecfilename” parameter.

---

### **voicerecformat**

(int)  
Recorded file compression.  
0: PCM wave stereo files with separate channels for in/out (default)  
1: raw gsm. 2 files will be generated for each call. One for the recorder file and another for the playback. These files can be played with players supporting gsm codecs for example [quicktime](#) (which works also as a browser plugin) or a winamp plugin is downloadable from [here](#).  
2: ogg/vorbis (optional, on request; module might not be included by default)

---

### **voicerecordingbuff**

(int)  
The maximum recorded file length.  
-1: dynamic, no limit  
1: max around 1 minute  
2: max around 2 minute  
...

Default is -1.

---

### **syncvoicerec**

(int)

How to synchronize the recording/playback side:

-1: Auto  
0: No (don't synchronize)  
1: Yes (fill with noise the other channel)  
2: Yes (wait for both side)  
Default: 2

## uploadretry

(int)  
Specify whether the file upload should be retried on failure if the voicerecording parameter is set to 2 or 3.  
0: no  
1: once  
2: until success  
Default: 1

## ftp\_addr

(string)  
FTP location for general storage (for example for settings, contactlists)  
Format: <ftp://USER:PASS@HOST:PORT/PATH/TO/THEFILE>  
Example: <ftp://user01:pass1234@ftp.foo.com/FILENAME>

The FILENAME part of the string will be replaced with the actual file name.

## http\_addr

(string)  
HTTP location for general storage (for example for settings, contactlists)  
Format: <http://www.yourdomain.com/storage/>  
(this is just an example URL format. This URL will not work. You need to change this to your own web address)

## webrtcserveraddress

(int)  
WebSocket server URL for WebRTC video if any. Example: <wss://rtc.myserver.com/sip>

## autocfgsave

(int)  
Configurations and statistics are stored in a local file to be reused in next sessions.  
This is not critical and the Java VoIP client will work just fine if this file is lost or deleted by the user.  
Sometime is useful to not allow configuration/settings storage on the user device.  
The autocfgsave option can be set to the following values:

- -2: disable all file write forced
- -1: disable file write
- 0: disable config storage
- 1: save only
- 2: load only
- 3: save and load

Default is 3.

## resetsettings

(boolean)  
Set to true to clear all previously stored or cached settings.  
Default is false.

## signalingport

(int)  
Specify local SIP signaling port to use.  
Default is 0 (a stable port which is selected randomly at the first usage)

*Note: this is not the port of your server where the messages should be sent. This is the local port for sip user agent.*

## ***rtpport***

(int)

Specify local RTP port base.

Default is 0 (which means signalingport + 2)

*Note: If not specified, then the Android SIP SDK will choose signalingport + 2 which is then remembered at the first successful call and reused next time (stable rtp port). If there are multiple simultaneous calls then it will choose the next even number.*

## ***incrtpport***

(int)

Increment RTP port for each call by this value.

Might be needed only with some misbehaving routers.

Default is 0.

*Note: You will still have a different RTP port for each simultaneous calls even if this is set to 0.*

## ***localip***

(String)

Specify local IP address to be used.

This should be used only on devices with multiple ethernet interface to force the specified IP.

Default is empty (autodetect)

## ***jittersize***

(int)

Although the jitter size is calculated dynamically, you can modify its behavior with this setting.

0=no jitter,1=extra small,2=small,3=normal,4=big,5=extra big,6=max

Default is 3

## ***allowspeedup***

(int)

Specify whether to enable audio playback speedup on high queue size.

(Instead of dropping packets, it might attempt to speed up the playback rate for a short time until queue size drops below threshold)

Possible values: -1: Auto Guess (default), 0: No, 1: Yes

## ***allowfirstdrop***

(int)

Specify whether to enable drop of RTP packets on media start.

Sometime the other end might start sending RTP before the media is opened at AJVoIP side resulting in accumulation of packets.

Dropping the first few packets will make the playback of the rest more smooth, but might result in some loss of audible media (usually up to 100 milliseconds)

Possible values: -1: Auto Guess (default), 0: No, 1: Yes

## ***maxjitterpackets***

(int)

You can limit the jitter buffer size with this setting.

*With the jittersize left as default (3) the maximum buffered packet count is limited to 8, so you might set this parameter to a lower value.*

*One packet means a received udp packet which might contain one or more audio frame.*

*For example when using G.729 the typical media stream are with 2 frames/packet. Each frame is 10 msec length.*

*A jitter limitation of 5 would mean maximum 100 msec to be cached. (while the default setting would allow 8 packet which means 160 msec)*

Default value is 99 (no limitation)

## ***increasepriority***

(boolean)

This will increase the priority for the whole thread-group which might help on slow CPU's or when other applications are generating high CPU load.

*Note: the priority of the threads handling media are increased regardless of this setting.*

Default is false.

## ***loglevel***

---

(int)

Tracing level. Values from 0 to 9.

You should set the default loglevel to 1 for production and 5 for test or development.

Loglevel 0 is not recommended as the Android SIP SDK will not even display important even notifications for the user in this case.

Loglevel 5 means a full log including SIP signaling.

Loglevel higher than 5 should be avoided (this can slow down the application).

The logs are sent to the following outputs:

- status display (only level 1 –these are the most important events that should be displayed also for the enduser)
- file if the canlogtofile parameter is set to true (\mwphonedata\webphonelog.dat)
- logcat if the logtoconsole parameter is set to true
- system log if the systemout parameter is set to true (System.Out)
- accessible for the GetLogs() API
- sent with notifications if the events parameter is 3

## ***logtoconsole***

---

(int)

Whether to send tracing to the java console (System.out.print or often referred as STDOUT).

Possible values:

- 0: no (disable log to console)
- 1: auto (depending on loglevel)
- 2: always (always log to stdout)

Default is 1.

## ***systemout***

---

(boolean)

Whether to send logs to standard output.

Default is false.

## ***logcat***

---

(boolean)

Whether to send logs to standard Logcat.

Default is true.

## ***canlogtofile***

---

(boolean)

With loglevel set to 2 or more, the logs are written also to a local file. To disable the log files, set the canlogtofile parameter to “false” (or set the “loglevel” to 1).

Default is false.

## ***capabilityrequest***

---

(boolean)

If set to true then will send a capability request (OPTIONS) message to the SIP server on startup. The serveraddress parameter must be set correctly for this to work. This method is useful to release the security restrictions when using the Android SIP library with the API and also to open the NAT devices.

Default value is false.

## ***natkeepalive***

---

(boolean)

If set to true then will send a short message (\r\n) to the SIP server on startup. The serveraddress parameter must be set correctly for this to work. This method is useful to release the security restrictions and also to open the NAT devices.

Deprecated since v.3.8.2

Default value is false.

## ***keepaliveival***

---

(int)

NAT keep-alive interval in milliseconds which is usually sent from register endpoints.  
Default value is 28000. (28 seconds)

---

### *recaudiobuffers*

(int)  
Number of buffers used for audio recording.  
Default is 7.

---

### *recaudiomode*

(int)  
Audio recording mode. 0 means default; 1 means event based; 2 means device poll.  
Default is 0.

---

### *useencryption*

(boolean)  
Set to true for encrypted communication (both media and signaling)  
This has nothing to do with standard SIP encryption and it works only with mizu server tunneling module.

---

### *callreceiver*

(int)  
How to handle incoming calls.  
Possible values:  
-1: auto  
0: disable all incoming calls  
1: enable incoming calls (while app is running; no background listener)  
2: enable also background calls (push or service implemented)  
Default is -1.

---

### *enablepush*

(int)  
This parameter is deprecated and to be used only for the softphones.  
Use the pushnotifications parameter or the [PushNotification](#) API to enable/disable push notifications.  
~~Specify whether to enable push notifications by default.~~  
~~Possible values:~~  
~~-1: auto~~  
~~0: disabled~~  
~~1: enabled auto~~  
~~2: enabled direct to SIP server~~  
~~3: enabled via gateway Default: -1~~

~~If set to 1, then will try push with your server (as described in RFC 8599 so your server must answer to REGISTER with Feature Caps: \*,+sip.pns="fcm") and if fails then it will try via push gateway.~~

For more details see the [push notifications](#) FAQ.

---

### *pushnotifications*

(int)  
Enable push notifications via as Google Firebase FCM.  
Possible values:  
-1=auto  
0=disabled  
1=enabled auto  
2=enabled direct (with your SIP server if it has push support)  
3=enabled via gateway

Default is -1 which means auto enable when required and possible. If FCM is available(if I have json file configured) and background service is not 1 AND there was incoming calls in the last 120 days or installed less then 120 days ago; otherwise it means no.  
We provides push service (free tier) for all our customers enabled by default (via gateway if your server doesn't support push notifications).

To configure push notifications, you might use the [PushNotification](#) API instead of these parameters.  
For more details see the [push notifications](#) FAQ.

### **fcmgateway**

---

(string)  
Specify FCM gateway to be used if a push gateway have to be used (instead of directly with SIP server).  
Default is: fcm.webvoipphone.com:35060

To configure push notifications, you might use the [PushNotification](#) API instead of these parameters.  
For more details see the [push notifications](#) FAQ.

### **packagename**

---

(string)  
Project ID. This is your application package name, used for export and upload to google market to be used also for push notifications.  
Default is: empty or loaded from your app context or com.mizuvoip.mizudroid.app with mizu gateways.

To configure push notifications, you might use the [PushNotification](#) API instead of these parameters.  
For more details see the [push notifications](#) FAQ.

### **fcmclientid**

---

(string)  
Your app token (token ID or Project ID returned by registering to the notification service) which can be received from your OS push/apns/fcm API.  
Default is empty string.

To configure push notifications, you might use the [PushNotification](#) API instead of these parameters.  
For more details see the [push notifications](#) FAQ.

### **pushtype**

---

(int)  
Specify what protocol to use for push notifications  
Possible values:  
-1: auto (1 with mizu servers, 2 with others or not sure)  
1: mizu proprietary X-MPUSH  
2: standard [RFC 8599](#)  
3: force RFC8599 even with our servers or secondary  
4: both  
Default is -1

In case if you are using a Mizu server, the AIVoIP can use the mizu proprietary protocol for push binding: X-MPSUH: a:packagename:clientid.  
Otherwise (with any third-party SIP servers) you should use the Push Notification for SIP standard as described in [RFC 8599](#) which will send pn-\* contact tags (Media Feature Tags) like pn-provider=fcm;pn-param=PACKAGENAME;pn-prid=TOKEN and will expect Feature-Caps: \*;+sip.pns="fcm" in the answer).

For the details about SIP push notifications see the "SIP signaling" chapter in the [VoIP Push Notifications](#) guide.  
For more details see the [push notifications](#) FAQ.

### **runservice**

---

(int)  
Set to 1 or 2 if your app is running as a service (or you are running the sipstack from a service) to enable some related optimizations.  
This might be necessary if your apps needs to be always available for incoming calls but for some reason you don't implement [push notifications](#).  
Possible values:  
-1: auto  
0: no  
1: background service  
2: foreground service  
Default: -1



Note: background services are heavily limited since API level 26 but AJVoIP implements all possible workarounds to bypass this limitation. Foreground services are more reliable since API level 26. Use a foreground if the always visible notification is acceptable for your user-case.

More details can be found [here](#).

### *scheduledwakeup*

---

(int)

Enable scheduled wakeup if running as a background service to help with background service [limitations](#) and doze/standby [limitations](#).

Possible values:

0: Never

1: Yes if running as service

2: Always force

Default: 1

More details can be found [here](#).

### *serviceclassname*

---

(String)

Used for scheduled wakeup.

Set this to the name of your android service class that will run in the background to be able to receive incoming calls.

Default value: empty

Example:

```
SetParameter("serviceclassname", "com.mycompany.appname.mainclass.myservice");
```

### *askforwhitelist*

---

(int)

Might ask the user to white-list your app if running as a background service to help with background service [limitations](#) and doze/standby [limitations](#).

Possible values:

0: No

1: Yes if running as service

2: Always force

Default: 1

More details can be found [here](#).

### *maxlines*

---

(int)

1: single line

2: unlimited

Default is: 2

### *fastexit*

---

(int)

Set cleanup speed and wait times.

0: slow but will more care about un-registration and cleanup

1: fast

2: very fast with no unregister

Default is: 1

### *events*

---

(int)

Defines the level of notifications:

0=no notifications,1=status and cdr,2=important events,3= all logs including SIP signaling messages (depending also on loglevel).

Default is 2.

(int)

Set to a value in seconds if you wish to receive extended periodic statistics for each line (STATUS notifications).

Default is 0 (no periodic statistics)

## FAQ

### How to get my own Android VoIP SDK?

1. Have a look at the description and pricing from the [SIP library home page](#)
2. Download and try the demo from [here](#). You might start with the [quick intro](#) and then read trough this [documentation](#).
3. Contact Mizutech at [info@mizu-voip.com](mailto:info@mizu-voip.com) with the following details
  - your VoIP server(s) address (ip or domain name). This will be hardcoded in your release; otherwise anybody could just download it from your and use as it owns)
  - your company details for the invoice (if you are representing a company)
4. Mizutech support will send your own AJVoIP build within one workday on your payment.  
The payment can be made from the [home page](#) pricing grid with paypal or credit card or by [wire transfer](#).

### What about support?

All licenses include also a support plan in the cost.

The support is done mostly by email. For “gold license” we offer 24/7 phone emergency support.

Maintenance upgrades are also free as included with your license plan.

Email to [info@mizu-voip.com](mailto:info@mizu-voip.com) with any issue you might have.

Guaranteed supports hours depend on the purchased license plan and are included in the price.

Once your initial 1-4 years support period expires, it can be increased by 2 years for around \$600 (This is optional. There is no need for any support plan to operate your AJVoIP as the library is shipped with life-time license).

*Note:*

- *We can't guarantee that all the listed features will work correctly in your environment (your SIP servers / integrated with your software). Please test the demo/trial version before purchase to make sure that all the functionality critical to your use-case works correctly.*
- *Our support answer time is usually up to one work-day for issues related to core functionality (such as connect/register and voice calls). We are trying to resolve all such issues as soon as possible. Issues affecting non-core features (such as call hold or presence) might be handled only in the upcoming new releases.*
- *Direct support is provided for the common features (voice calls, chat, dtmf and others) and not for extra features (such as presence or video). Direct support is not provided for the issues described in the [known limitations](#) section. If you have some special must-to-have requirement, we recommend to test with the [demo](#) version before purchasing your license. However we appreciate all bug reports and we are constantly working on our software shipping new features, improvements and bug fixes with each new release.*
- *Mizutech doesn't provide direct server side support. Although AJVoIP is known to work well with all common SIP servers (including Asterisk, FreeSWITCH and many others), your servers have to be managed by you and we are not responsible for proper configuration of your servers. However, in case if there is any incompatibility issue then we might be able to help you with the resolution if you send us the related logs.*

### What I will receive once I have made the payment for Android VoIP SDK?

You will receive the followings:

- The AJVoIP library itself. This is one single file usually named as “AJVoIP.jar” or “AJVoIP.aar”
- Latest documentations
- Usage examples
- Invoice (on request or if you haven't received it before or during payment)
- Support on your request according to the license plan

[More details.](#)

### Can Mizutech do custom development if required?

Yes, please contact us at [info@mizu-voip.com](mailto:info@mizu-voip.com).

Note: Please contact us only with AJVoIP related or VoIP specific projects. We are highly specialized for VoIP development thus we will not accept general app development projects which can be done by any developer or team (We don't handle tasks such as building user interface or design elements).

## Is it working with any VoIP servers?

Yes. The VoIP SKD uses the SIP protocol standard to communicate with VoIP servers and sofswitches. Since most of the VoIP servers are based on the SIP protocol today, AJVoIP should work without any issue. AJVoIP have been tested with numerous other SIP stack (software/hardware) and we invest extra effort to achieve maximum compatibility even with misbehaving SIP implementations.

If you have any incompatibility problem, please contact [info@mizu-voip.com](mailto:info@mizu-voip.com) with a problem description and a detailed log (loglevel set to 5). For more tests please send us your VoIP server address with 3 test accounts.

## How is the call quality?

Short answer: "better than Skype"

Long answer:

The library is capable for perfect voice quality if that is possible in your environment (server/peer codec support, network link quality, etc). Otherwise it aims to produce the best possible call quality achievable depending on the circumstances.

AJVoIP includes wide-band [OPUS](#) and Speex codec which are capable to offer a perfect call quality (MOS score of 6).

Of course, these have to be supported also by the peer to be used. PSTN networks usually has support only for narrowband codec (such as G.729, GSM, iLBC or G.711), so the call quality will be lower here (but still better than traditional phones if the user connection fulfills the minimal bandwidth and quality required for VoIP).

The media stack implements best practices for network and audio device handling to minimize the total delay.

A wide range of audio enhancement algorithms are also implemented such as AEC, denoise, PLC and AGC.

AJVoIP is also capable to auto-fine-tune itself to the circumstances by default (based on device capabilities, CPU speed, network bandwidth/quality, peer/server capabilities), but you can also force any settings with the parameters (such as codec, framesize, aec, etc).

## Is AJVoIP using any Mizutech service or will contact Mizutech servers?

The Android SIP SDK will connect to your voip server directly. No any intermediary app server is involved.

AJVoIP will not "call to home" and will not send any sensitive information to Mizutech servers.

AJVoIP might contact Mizutech servers for the following reasons:

- demo versions might contact Mizutech licensing servers time to time. This is completely removed in final builds (after your order)
- AJVoIP will use a random stun server by default hosted by Mizutech. This "fast stun" protocol is usually not required for normal functionality so you might just disable it (set the "use\_fast\_stun" parameter to 0) or set the "stunserver" parameter to your stun server. (However these can improve the connectivity if your VoIP server is not NAT friendly so better to leave it as is. Mizu services (non) availability can't alter the usability of your product)
- Push Notifications: if you don't implement your own push notification service then AJVoIP might use the Mizu push notification gateway which we offer for all our customers (free tier). This can be disabled or replaced with your own implementation.

## Is there any way to get the source code?

The Android VoIP SDK is a close-source application. The source code is available only for internal usage at an additional higher cost.

## How to register?

SIP registration means connecting to your SIP server and authenticating. From this procedure your SIP server will learn your application address and can route incoming calls to your application (or other sessions, such as chat, presence, voicemail, etc).

The SIP stack auto-start behavior can be altered with the [startsipstack](#) setting or you can use the [Start](#) function to launch the instance explicitly.

When started, the SIP stack by default (unless you set the [register](#) parameter to 0) will automatically register to your SIP server if you configured the [SIP account details](#) (serveraddress, username, password and any other parameters that might be required such as the proxyaddress and sipusername).

Otherwise you might disable auto-start ([startsipstack](#)) and/or the auto register ([register](#)), [pass](#) the above parameters dynamically from your code and use the [Start](#) and/or the [Register](#) function to initiate the start/connect/register procedure.

The registration success or failure can be obtained from the STATUS notifications.

- Proceeding notification strings:
  - Register...
  - Registering... (or "Register...")

- Register Failed
- Success notification strings:
  - Registered
  - Registered.
- Failure notification strings:
  - Connection lost
  - No network
  - Server address unreachable
  - No response from server
  - Server lost
  - Authentication failed
  - Rejected by server
  - Register rejected
  - Register expired
  - Register failed

The registered state can be requested with the [IsRegistered](#) or [IsRegisteredEx](#) API.

The failure reason can be also obtained (instead of the above STATUS strings) by using the [GetRegFailReason](#) API.

Check [this FAQ point](#) if you are having problems with connect/register.

## Multiple account registration

The VoIP SDK is capable to register multiple accounts at the same time. This can be useful to be able to make and receive calls from multiple accounts or multiple servers.

You can configure multiple accounts using the [extraregisteraccounts](#) parameter or the [RegisterEx](#) function passing a string with the accounts fields. Fields are to be separated by comma and multiple accounts separated by semicolon.

The following fields can be passed:

[serveraddress](#), [username](#), [password](#), [registerinterval](#), [proxyaddress](#), [realm](#), [authusername](#)

Most of these fields are optional. The mandatory parameters are the username, password (and the serveraddress if that it is different from your main SIP server).

The SIP accounts can be configured by parameters in the following way:

[serveraddress](#), [username](#), [password](#), [registerinterval](#): primary account  
[serveraddress2](#), [username2](#), [password2](#), [registerinterval2](#): second account  
[serveraddress3](#), [username3](#), [password3](#), [registerinterval3](#): third account  
 ...  
[serveraddressN](#), [usernameN](#), [password](#), [registerintervalN](#): N account

Or via the [RegisterEx\(String accounts\)](#) API call where the accounts are passed as string in the following format:

[server](#),[usr](#),[pwd](#),...;[server2](#),[usr2](#),[pwd2](#), ...;  
 (accounts separated by ; and parameters separated by , )  
 Example: [mysipclient.RegisterEx\("myserver2.com,user2,pwd2;myserver2.com,user3,pwd3,120,,,sipusername3"\)](#);

Or via the ["extraregisteraccounts"](#) parameter which have to be set like this:

[server](#),[usr](#),[pwd](#),...;[server2](#),[usr2](#),[pwd2](#)...;  
 Example: [mysipclient.SetParameter\("extraregisteraccounts","myserver2.com,user2,pwd2;myserver2.com,user3,pwd3,120,,,sipusername3"\)](#);

Notes:

- Up to 99 secondary accounts can be used this way
- All other parameters are applied globally for all account (there is no per account profile). The "proxyaddress", if set, will be applied for primary account only
- STATUS about registrations are not reported from secondary accounts (but you will receive call state STATUS notification while in call as normally)
- If you need easier control for the separate accounts then you can also just launch AJVoIP multiple times (multiple instances) with different parameters (Multiple instances per account requires a bit more system resources –some more RAM for each instance- but it might be more convenient for you)

## How can I make a call?

- Make sure that the "serveraddress" parameter is set correctly (otherwise you will be able to make calls only to direct SIP URI).
- Optionally: Register to the server. This can be done automatically if the "username" and "password" parameters are preset. Alternatively you can register from API (Register) or just let the user to fill in the username/password fields and click on the "Connect" button. If AJVoIP is registered, then it can already accept incoming calls (it will do it automatically, or you can handle incoming calls from your application, or you can entirely disable incoming calls)
- Now you can make outgoing calls in the following ways:
  - Automatically with AJVoIP start. For this you will have to preset the username, password, autocal and callto parameter. Then AJVoIP will immediately launch the outgoing call when starts (usually with your page load)
  - Just let the users to enter a called number and hit the "Call" button
  - or just call the [Call](#) function (from user button click or from your business logic)

Optionally on call you might set the following flags (for example if you have a separate call page activity, then you might set these from onCreate):

```
getWindow().addFlags(WindowManager.LayoutParams.FLAG_DISMISS_KEYGUARD);
getWindow().addFlags(WindowManager.LayoutParams.FLAG_SHOW_WHEN_LOCKED);
getWindow().addFlags(WindowManager.LayoutParams.FLAG_TURN_SCREEN_ON);
getWindow().addFlags(WindowManager.LayoutParams.FLAG_KEEP_SCREEN_ON);
if(Build.VERSION.SDK_INT >= 24) getWindow().setSustainedPerformanceMode(true);
```

Check [this FAQ point](#) if you are having problems initiating calls.

## How to handle incoming calls?

To be able to receive incoming calls, make sure that you are [registered](#) to your SIP server first. Then you can easily test for example by using any third party [softphone](#) and make calls to your android SIP username (or extension id or full URI, as required by your server).

In your project all you have to do is to watch for incoming [ringing STATUS](#) notifications and from there you can show any user interface (activity) as you wish.

If you follow the [example code](#), you receive the notifications in the public void ProcessNotifications(String msg) function. You can find the possible strings that can be received at the “[Notifications](#)” chapter in the documentation.

To catch incoming calls, you have to look (string parse) for [STATUS](#) messages with “[Ringing](#)” text (second parameter is the state text) and the [endpointtype](#) (forth parameter) set to 2 (means incoming).

For example the following status means that there is an incoming call ringing from 2222 on the first line:

[STATUS,1,Ringing,2222,1111,2,Katie,\[callid\]](#)

AJVoIP is capable for automatic line management so if you don't wish to handle lines [explicitly](#) in some specific way, then you can ignore all notifications, except those where the line (first parameter) is [-1](#) (the global state).

If you wish to auto accept all incoming calls, you can set the [autoaccept](#) parameter to true. Otherwise use the [Accept](#) API to connect the call (or the [Reject](#) API to disconnect). Check the [parameters](#) to find out more call divert settings, such as auto-answer or forward if needed.

Check [this FAQ point](#) if you are having problems receiving incoming calls.

## Project dependency issues

Check the followings in case if you are unable to build your project because dependency issues.

For example you might receive an error something like this:

Unable to resolve dependency for ':app@debug/compileClasspath': Failed to transform file 'AJVoIP.aar' to match attributes {artifactType=android-exploded-aar} using transform ExtractAarTransform

This has less to do with our aar and it is a gradle bug.

Possible solutions:

1. Clean project  
Rebuild project
2. <https://github.com/golang/go/issues/23307>
3. <https://stackoverflow.com/questions/45138391/failed-to-transform-file-45907c80e09917e1b776adf038505958-to-match-attributes>
4. Make sure your machine is connected to the internet.  
Go to File -> Settings & expand Build, Execution, Deployment -> Gradle -> UNCHECK Offline work -> OK  
Go to File -> click on Invalidate Caches / Restart -> Invalidate & Restart
5. Upgrade android studio and tools to latest version
6. Just create a new project and add our aar to it and the code from MainActivity.java.

## Failed outgoing calls

First of all you should check the logs (logcat) to see any ERROR and the SIP signaling.

For outgoing call you should see an INVITE sent to server (or peer) and a 2xx response (usually 200 OK) on call connect or other response (4xx, 5xx, 6xxx) on call failure. Some server requires previous successful registration (REGISTER) to allow calls.

Some servers has problems with codec negotiation (requiring re-invite which is not support by some devices). In these situations you might enable only one codec which is supported by your server by setting the codec parameter (for example codec: PCMU).

AJVoIP by default doesn't allow cross-domain calls. For example if you are registered as [a@A.com](#) (to A domain) then you will not be able to make direct calls to [b@B.com](#) (to B domain). Contact mizutech support if you need this use-case to remove the limitation.

## Can't connect to SIP server

If the SDK cannot connect or cannot register to your SIP server, you should verify the followings:

- You have set your SIP server address:port correctly
- Make sure that you are using a SIP [username/password](#) valid on your SIP server
- Make sure that the [autostart](#) parameter is true and the [register](#) parameter is 1 or 2. Otherwise use the [Start\(\)](#) and/or [Register\(\)](#) functions explicitly.
- Make a test from a regular SIP client such as [mizu softphone](#) or [x-lite](#) from the same device (if these also doesn't work, then there is some fundamental problem on your server not related to our library or your device firewall or network connection is too restrictive)
- Check if some firewall, NAT or router blocks your device or process or the SIP signaling
- Check the [logs](#)
- If there are no any answer for the REGISTER requests, turn on your server logs and look for the followings:
  - The REGISTER reaches your server?
  - Is there any response triggered (or some error)?
  - If answer is triggered, is it sent to the correct address? (it should be sent to the exact same address from where the server received the REGISTER request)
  - The answer packet reach the client PC? You can use [Wireshark](#) to see the packets at network level.
- [Send us](#) a detailed client side log if still doesn't work with loglevel set to 5 (from the browser console or from softphone skin help menu)

## Calls are disconnecting

If the calls are disconnecting after a few second, then try to set the "invrecorderoute" parameter to "true" and the "setfinalcodec" to 0.

If the calls are disconnecting at around 100 second, then most probably you are using the demo version which has a 100 second call limit.

See the CDR and the log about the details.

## Blank screen or freezing on calls

Ask for RECORD\_AUDIO permission from your app before to make calls.

## Known limitations

- No technical support for Bluetooth related functionality (we provide it "as is" since incompatibility issues might occur due to the high device fragmentation)
- The video module is provided "as-is" with no specific support. Find more details [here](#).
- The full STUN specification is not implemented due to size and performance considerations (a fast and light STUN version is used when needed which always outperforms the standard STUN implementations with no drawbacks)

## Media statistics

Media statistics means RTP/RTCP level details, which can be used to analyze call quality or to display a call quality indicator.

- Basic details: are received with the [STATUS](#) notifications such as total rtpsent, rtprec, rtploss, rtplosspercet and server statistics if reported. These and more is also received with the [RTP](#) LOG notification.
- Quality reports: can be sent as [RTPSTAT](#) notifications if enabled by the [rtpstat](#) parameter. Alternatively it can be requested with the [RTPStat](#) function call.
- Logs: You can also see more details in the logs such as total rtp statistics reports for calls longer then 7 seconds if the loglevel is at least 3 as [EVENT, rtp stat: sent X rec X loss X X%](#) or the [RTP](#) notification. If you set the "loglevel" parameter to at least "5" than the important rtp and media related events are also stored in the logs. You might search for "call details" at the log which also includes media related reports after each call.

## Voice activity detection

AJVoIP has built-in VAD (voice activity detection) algorithm included.

The talking/silence state of both the local user and the remote peer can be reported.

To enable VAD reports, set the [vad](#) parameter to 4.

Once this is set, you can receive the VAD state either by calling the [VAD function](#) or by the [VAD notifications](#) if the vadstat parameter is set to 3 or 4. For the notifications interval you might also adjust the vadstat\_ival parameter after your needs (default is 3000 in milliseconds, which means a VAD report in every 3 seconds). If the vadstat is set to 4 then it will report the state also when changed from silence to speaking or inverse.

## NAT settings

*In the SIP protocol the client endpoints have to send their (correct) address in the SIP signaling, however in many situations the client is not able to detect it's correct public IP (or even the correct private local IP). This is a common problem in the SIP protocol which occurs with clients behind NAT devices (behind routers). The clients have to set its IP address in the following SIP headers: contact, via, SDP connect (used for RTP media). A well written VoIP server should be able to easily handle this situation, but a lot of widely used VoIP server fails in correct NAT detection. RTP routing or offload should be also determined based in this factor (servers should be always route the media between 2 nat-ed endpoint and when at least one endpoint is on public IP than the server should offload the media routing). This is just a short description. The actual implementation might be more complicated.*

You may have to change Java VoIP toolkit configuration according to your SIP server if you have any problems with devices behind NAT (router, firewall). If your server has NAT support then set the use\_fast\_stun and use\_rport parameters to 0 and you should not have any problem with the signaling and media for AJVoIP behind NAT. If your server doesn't have NAT support then you should set these settings to 2. In this case AJVoIP will always try to discover its external network address.

Example configurations:

If your server can work only with public IP sent in the signaling:

- use\_rport 2 or 3
- use\_fast\_stun: 1 or 2 or 4 (recommended is 2)

If your server can work fine with private IP's in signaling (but not when a wrong public IP is sent in signaling):

- use\_rport 9
- use\_fast\_stun: 0
- optionally you can also set the "udpconnect" parameter to 1

Asterisk is well known about its bad default NAT handling. Instead of detecting the client capabilities automatically it relies on pre-configurations. You should set the "nat" option to "yes" for all peers.

More details:

- <http://www.voip-info.org/wiki/view/NAT+and+VOIP>
- <http://www.voip-info.org/wiki/view/Asterisk+sip+nat>
- [http://www.asteriskguru.com/tutorials/sip\\_nat\\_oneway\\_or\\_no\\_audio\\_asterisk.html](http://www.asteriskguru.com/tutorials/sip_nat_oneway_or_no_audio_asterisk.html)

## Server failover/fallback

Use the following settings if you have 2 voip servers:

- serveraddressfirst: the IP or domain name of the first server to try
- serveraddress: the IP or domain name of the next server
- autotransportdetect: true
- enablefallback: true

In this way java voip framework will always send a register to the first server first and on no answer will use the second server (the "first" server is the "serveraddressfirst" at the beginning, but it can change to "serveraddress" on subsequent failures to speed up the initialization time)

Alternatively you can also use SRV records to implement failover or load balancing.

## I have call quality issues

It is normal to get cropping audio with debug builds running from the IDE on your phone and especially on emulator. Call quality during test sessions can be improved by lowering the log level, disabling AEC and denoise and forcing a low complexity codec such as PCMU. If you wish to focus on call quality tests then you should build a release version and run it normally on your phone, not from your development environment such as the Android Studio IDE.

Call quality is influenced primarily by the followings:

- Codec used to carry the media (PCMU, PCMA requires the less CPU but more bandwidth; G.729 and OPUS wideband requires more CPU but it is more optimized for bandwidth). The best possible call quality can be achieved with OPUS wideband if you are using a release build
- Network conditions (check also your upload packet loss/delay/jitter)

- Hardware: enough CPU power and quality microphone/speaker (try a headset, try on another device)
- AEC and denoise algorithms increases the CPU load especially under debug
- Missing (disabled) AEC and denoise might result in suboptimal call quality
- Log details: high loglevel might decrease the sound quality. You should set the loglevel to 5 or lower
- Debugging: release versions have better quality due to optimizations

If you have call quality issues then the followings should be verified:

- whether you have good call quality using a third party softphone from the same location (try X-Lite for example). If not, than the problem should be with your server, termination gateway or bandwidth issues.
- make sure that the CPU load is not near 100% when you are doing the tests
- watch for [RTP statistics](#)
- make sure that you have enough bandwidth/QoS for the codec that you are using
- change the codec (disable/enabled codec's with the codec/prefcodec or the use\_XXX parameters)
- run your app on a real device (your phone) and not on the simulator
- force a low complexity codec such as PCMU for your debug builds and test sessions
- check the AJVoIP logs (check audio and RTP related log entries with loglevel 5)
- set the loglevel to 1 (or up to 5)
- wireshark log (check missing or duplicated packets)

## Performance optimizations

The SDK by default comes with optimal default value but in some circumstances you might need to further optimize for performance.

If you are running the SDK on some ancient device or any device with low-end CPU or lower-powered devices, you can optimize the performance with the following settings:

- Make sure that no other processes on your device are running with abnormally high CPU usage (remove or optimize other processes that are unnecessarily consuming the CPU)
- Prioritize low computational codecs with the following settings:  
`use_pcmu=3 use_pcma=2 use_g729=1 use_gsm=2 use_speex=1 use_speexwb=1 use_speexuwb=0 use_opus=1 use_opuswb=1 use_opusuwb=0 use_opusswb=0 use_ilbc=1`
- Set the loglevel to 1 (High log levels will slow down the SDK. But don't set it to 0)
- Set the following parameters to 0 to lower the number of threads (especially if there are only 1 or 2 CPU cores available for AJVoIP):  
`audiorecthread, audioplaythread, audioplaythread2`
- Disable extra audio processing by setting the followings to 0: `aec, aec2, denoise, agc, silencesuppress`  
(In case if you don't wish to completely disable AEC, then just fine-tune the `aec, aec2` and `aectype` settings. Avoid full software `aec`.)
- Increase the `audioqueuemaxsize` value. Default is 40. Increasing it can help with short CPU spikes and packet bursts but might increase the playback delay
- Additional optimizations:
  - `codeccodecframecount`: 2 (or even 4; might be incompatible with some bogus servers)
  - `voicerecording`: 0
  - `syncvoicerec`: 0
  - `vad`: 1
  - `plc`: false
  - `rtcp`: false
  - `aectype`: none
  - `enablepresence`: 0
  - `registerinterval`: 300
  - `keepaliveinterval`: 50
  - `timer`: 20 (not recommended)
  - `timer2`: 20 (not recommended)
  - Set the `cpuspeed` parameter to 700 or less (or some other value between 300 and 2000)
- In case if you are using the SDK for some special purpose with on way audio then you should to set the `useaudiodevicerecord` or `useaudiodeviceplayback` parameters to false. In this case you might also set the `mediatimeout` parameter to 0.

It might be possible that one or two of the above already fixes any performance problems on your devices. In that case it is not necessary to change all of these settings.



## I have one way audio

---

1. Review your server NAT related settings
2. Set the “setfinalcodec” parameter to 0 (especially if you are using Asterisk or OpenSIPS)
3. Set use\_fast\_stun, use\_fast\_ice and use\_rport to 0 (especially if you are using SIP aware routers). If these don’t help, set them to 2.
4. If you are using MizuVoIP server, set the RTP routing to “always” for the user(s)
5. Make sure that you have enabled all codec’s
6. Make a test call with only one codec enabled (this will solve codec negotiation issues if any)
7. If you still have one way audio, please make a test with any other softphone from the same PC. If that works, then contact our support with a detailed log (set the “loglevel” parameter to 5 for this)

## No ringback tone

---

Depending on your softswitch configuration, you might not have ringback tone or early media on call connect.

There are few parameters that can be used in this situation:

- set the “changesptoring” parameter to 3
- set the “natopenpackets” parameter to 10
- set the “earlymedia” parameter to 3
- change the use\_fast\_stun parameter (try with 0 or 2 or 4)
- set the “nostopring” parameter to 1
- set the “ringincall” parameter to 2

One of these should solve the problem.

## The remote party hear itself back (echo)

---

### About

Echo suppression and cancellation are special voice processing algorithms to prevent the audio played on the speaker to be recorded and sent back to the other party resulting in echo.

The perceived echo depends on many factors:

- The AEC algorithms used by AJVoIP and on the other end
- Network delay
- Device hardware capabilities (on both the AJVoIP side and the other side)
- Speaker device
- OS audio processing and audio driver
- Room characteristics

Please note that when you hear echo with AJVoIP, the culprit is usually the other end as there is nothing to solve the echo problem if it is already present in the incoming stream. The solution in this case is to use AEC capable devices also for the peers.

AEC is important only if a speaker/loudspeaker/speakerphone is used. If the user will make a normal call with off-speaker or using a headset than echo is generated only if the internal speaker or the headset is broken.

Also it is possible that some software is capable to suppress echo under specific circumstances and other software might fail in the same circumstances but might have better success in other circumstances.

### Success rate

Please note that echo cancellation is not an exact science and there is no perfect algorithms for 100% echo cancellation.

AJVoIP includes five different AEC/AES algorithms:

- software: two separate software based AEC algorithm (requires extra CPU processing)
- hardware: android hardware aec capabilities (not supported on all phones)
- fast: a fast software aec implementation (used preferably on slow/old devices or in addition for the above algorithms)
- volume: this will decrease the volume when speech detected from other end (using VAD)

After our tests with numerous hardware the AJVoIP media stack is capable to eliminate more than 90% of the echo with around 92% success rate.

### Settings

Echo cancellation in AJVoIP is usually turned on by default when necessary (depending on the playback device used and might be disabled by default on devices with very slow CPU such as ancient or low-budget phones).

You might adjust the following settings to fine-tune the AJVoIP side AEC if there is echo generated by AJVoIP in your environment:

- Set the [aec](#) parameter to **2**.
- Set [aectype](#) parameter after your needs. For example you might set it to **software,hardware,fast,volume** to apply all suppression algorithms
- For better quality you can also set the [denoise](#) parameter to **1**.

To completely disable AEC, set the [aec](#) parameter to **0** and the [aectype](#) to **none**. This might be used to save CPU time in circumstances when no echo is possible such as have only one way audio (like IVR calls) or there is no loudspeaker usage.

## RTC video

---

Video requires RTC capabilities (handled automatically by AJVoIP or you can set your own `webrtcserveraddress`).

Details:

VoIP Video streaming is a moving target. In the past we had H.263, nowadays H.264 and VP8 but soon the industry will move to H.265, VP1 and VP9. To avoid constant rewrite and optimizations to the latest preferred standards we decided to take full advantage of the WebRTC capabilities already found on all platforms. AJVoIP uses the WebRTC module offered by the Android browser via a WebView, thus always up to date but requiring RTC capabilities for SIP compatibility. This is handled with the default settings or you can use the [webrtcserveraddress](#) parameter if you wish to specify your own WebRTC server endpoint (websocket listener). A simple way to test video functionality is to make a WebRTC call from Chrome to check if it works as expected or at least [test](#) your Chrome browser WebRTC capabilities.

Video re-INVITE is not currently supported (usage with SIP devices which are capable to initiate or accept the video from start as upgrading a voice call to video will not work). RTC uses the latest standards for video negotiation and byte stream format thus might not be compatible with all SIP devices as it enforces a strict video codec negotiation that might not be supported by the peer device.

If video is your main use-case we recommend testing it first in your environment before to purchase to make sure that it works with your server/ devices. (You can make a quick test with the MizuDroid softphone downloadable from the Google Play as that is based on this AJVoIP library).

We provide the video module as-is with no specific support as we rely on the platform RTC capabilities here with the limitations mentioned above, but you can assume that android will always ship with the latest video tech which should provide optimal performance and compatibility with the latest devices.

Required [permission](#): CAMERA

Codec support: depends on the RTC stack. Usually H264, VP8 and VP9.

Video related parameters: [video](#), [vcodec](#), `video_bandwidth`, `video_size` parameters, `webrtcserveraddress`

Video related API's: [VideoCall](#), [AcceptVideo](#), [RemoveVideo](#), `SetVideoDisplaySize`, `IsIncomingVideo`

## Chat is not working

---

Make sure that your softswitch has support for IM and it is enabled. The Java SIP client is using the MESSAGE protocol for this from the SIP SIMPLE protocol suite as described in [RFC 3428](#).

Most Asterisk installations might not have support for this [by default](#). You might use [Kamailio](#) for this purpose or any other [softswitch](#) (most of them has support for RFC 3428).

## AJVoIP doesn't receive incoming calls

---

To be able to receive calls, AJVoIP must be registered to your server.

Once the SIP client is registered, the server should be able to send incoming calls to it.

The other reason can be if your server doesn't handle NAT properly: Please try to start AJVoIP with `use_fast_stun` parameter set to 0 and if still not works then try it with 2.

If you wish to be able to always accept incoming calls (even when the user is not actively using the app), then implement all-time availability as discussed below.

## All-time availability

---

To be able to accept calls, IM and other notifications, the server needs to be capable to deliver the SIP signaling messages to your application.

Normally your application is "connected" to your SIP server with an active UDP or TCP register session thus the SIP server is capable to send call connect, IM and other messages via these streams.

New Android OS versions heavily restricts apps running in the background and usual applications will just stop running when not in foreground or actively used by the user.

To be able to receive incoming call while your app is in background, closed, standby or the device is in doze or sleeping state, you have two options:

- [Run as a service](#)
- Enable [voip push notifications](#)

## Run as a service

One way to implement all-time availability (beside using push notifications) is to continuously run the sip stack, keeping your register session alive, always connected to your SIP server using UDP (with keep-alive to bypass NAT's) or a TCP connection. This is necessary because to be able to always accept incoming calls or text message (even when the app is not opened) your SIP server needs to be capable to deliver the INVITE/MESSAGE/other SIP messages to your application.

This should be used only if you don't wish to enable push notification for some reason or push notifications can't be used for your use-case for some reason.

This can be achieved by running the SIP stack from a [service](#).

You need to have an android service running in the background and on an incoming call you can start your activity from that service using the below code:

```
Intent intent = new Intent(this, MyActivity.class);
intent.addFlags(Intent.FLAG_ACTIVITY_NEW_TASK);
startActivity(intent);
```

Running the app (or just the SIP stack) as service is a convenient mode to achieve availability and AJVoIP implements all best practices for battery optimizations thus requiring minimal CPU and energy while running in idle (slow down timers, auto-lowering the priority of it's threads and other optimizations).

To be able to keep the register session alive the app needs to fulfill the followings conditions:

- actually running (not killed/closed or put in a doze or sleep state)
- capable to acquire wake lock
- capable to acquire wifi lock (if there is no mobile data or the user prefers Wi-Fi)

The only problem is that background services are severely [restricted](#) in latest Android versions and apps are also affected by [Doze and Standby limitations](#). Fortunately there are workarounds and good practices supported by AJVoIP and additional techniques that you might implement as described below.

The followings **should** implemented the followings in your app:

- Set the [runservice](#) AJVoIP parameter to 1 or 2
- Set the [serviceclassname](#) AJVoIP parameter to your service class name
- Run the service with START\_STICKY and start the SIP stack from the service

The followings **might** be implemented/handled by your app:

- A simple way to circumvent the [background service limitations](#) since API level 26 dosing or sleep is to just run a [foreground service](#) (instead of a background service). This is a more reliable way to make it always available but a non-removable notification will be displayed while the app is running.
- You might also [start your app service at boot](#) (requires the RECEIVE\_BOOT\_COMPLETED permission. Since API level 26 only foreground services can be automatically started. More details: [1,2,3](#))
- From API level 26 (Android Oreo) the OS prevents the use of startService() method to start the service from background. If you call [startService\(\)](#) from background on Android O, you will get an IllegalArgumentException. In this case you might just catch the exception and start a foreground service instead using the [startForegroundService\(\)](#) API.
- From API level 29 (Q) you should only use a foreground service (background services are not allowed to run continuously for networking/audio as it would be required for VoIP)
- Optionally you might implement a [tricky technique](#) to always restart your service if killed by the OS (just make sure to not restart if the user explicitly unregistered and stopped your application)
- Optionally check for [isBackgroundRestricted](#) and ask the user to release the [restrictions](#)

The followings are implemented/handled by AJVoIP:

- Acquire wake lock / wifi lock: by default this is handled by the AJVoIP itself with no further actions required from your side. It can be finetuned with the forcewifi, cpupartiallock and cpualwayspartiallock settings if for some reason the default behavior is not suitable for your use-case
- The SIP stack is also capable to auto wake-up by using the Android [alarm manager](#) capabilities. This will also help in some circumstances, but this kind of alarms are limited usually to a 10 minute intervals. You can enable/disable this with the [scheduledwakeups](#) parameter.
- Ignore batter optimizations: latest Android versions might automatically enforce Doze or Standby. Whitelisting your application can be asked with the ACTION\_REQUEST\_IGNORE\_BATTERY\_OPTIMIZATIONS which can be done from your code or just set the [askforwhitelist](#) parameter to 1.  
Note: this is a dangerous permission and google might remove your app from the Google Play if used for no valid reason as described at the end of [this page](#).

In case if you wish to do this from your own app for some reason, set the askforwhitelist to 0 and use this copy-paste code:

```
PowerManager pmanager = (PowerManager) getSystemService(Context.POWER_SERVICE);
if (Build.VERSION.SDK_INT >= Build.VERSION_CODES.M)
```

```

{
    if (!lpmanager.isIgnoringBatteryOptimizations(getPackageName()))
    {
        //Ask the user to disable battery optimization
        Intent intent = new Intent();
        intent.setAction(Settings.ACTION_IGNORE_BATTERY_OPTIMIZATIONS_SETTINGS);
        startActivity(intent);
    }
}

```

To summarize, there are the following ways to achieve always availability:

- Enable push notifications: Recommended method to enable always availability (discussed below). If enabled, then there is no need to run any service.
- Using a foreground service: This is a simple and reliable method with the drawback of a non-removable notification displayed on the device home screen
- Using a background service: A bit more tricky and workarounds required as describe above, but fully supported by AJVoIP
- Optional tricks such as auto restart and asking the user to reconfigure their phone settings to allow your app to run in the background
- Not using any service: You can just enable push notification support (discussed below), thus your app doesn't have to be run continuously (zero battery utilization)

## VoIP Push notifications

VoIP Push notification is an effective solution to wake up/launch your closed or sleeping application on incoming SIP call or text message without the need to run your application in the background and to keep a persistent connection (or frequent UDP keep-alive or re-register) with the SIP server/proxy.

The SIP library has full support for push notifications which can be negotiated directly with your server (if your server has push support) or via gateway (if your server doesn't support push [RFC 8599](#))

There are two ways to enable/disable/configure push notifications.

- Using the API: call the [PushNotification](#) function (recommended)
- Using parameters: configure the [pushnotifications](#) / [fcmgateway](#) / [packagename](#) / [fcmclientid](#) parameters.

Push notifications can use the mizu proprietary protocol (with mizu servers/gateways using the X-MPUSH header) or the Push Notification for SIP standard described in [RFC 8599](#). This protocol to use is selected automatically by default or you can force explicitly with the [pushtype](#) parameter.

### Push notifications with your SIP server

Push Notification for SIP is described in [RFC 8599](#).

If your server has push notification support then AJVoIP will send all the required details (Project ID, Registration token) with the SIP signaling (pn-\* media feature tags in Contact) and your server must send a push notification to AJVoIP (via FCM) to wake up the app before incoming calls and it can also send IM chat messages as push notifications (along the usual SIP MESSAGE).

In case if your server doesn't have push support then you can still use push notifications via gateway as described below.

### Push notifications via Mizu gateway or service

If you use your own (or other) SIP server which doesn't have push notification support (or you don't wish to use it's push capabilities) then you can use the mizu [VoIP push notification gateway](#) or free service to handle push notifications for your app (AJVoIP also comes with a free tier push service to handle push notifications).

In this case follow the instructions at the "AJVoIP -Mizu PUSH service" from the [VoIP Push Notifications](#) guide.

### Push notifications with Mizu servers

Push notification support is included in all Mizu server side products. In case if you use a Mizutech server, then you can implement push notifications as described at the [VoIP Push Notifications](#) guide "AJVoIP" chapter.

More details about VoIP push notifications can be found [here](#) and [here](#).

## What is the best codec?

There is no such thing as the "best codec". All commonly used codec's present in AJVoIP are well tested and suitable for IP calls. This depends mainly on the circumstances.

Usually we recommend G.729 since this provides both good quality and good compression ratio.

If G.729 is not available in your license plan, than the other codecs are also fine (GSM, speex, iLBC)

Otherwise the G711 codec is the best quality narrowband codec. So if bandwidth is not an issue in your network, than you might prefer PCMU or PCMA (both have the same quality)

Between AJVoIP users (or other IP to IP calls) you should prefer wideband codec's (this is why you should always leave the opus and speex wideband with the highest priority if you have calls between your VoIP users. These will be picked for IP to IP calls and simply omitted for IP to PSTN calls) To calculate the bandwidth needed, you can use [this tool](#). You might also check this blog entry: [Codec misunderstandings](#)

## What is the default codec priority?

The codec priority order is calculated automatically based on circumstances (CPU, device capabilities, network). The AJVoIP library does a good job to always select the optimal codec set so you should change the codec priorities only if you have some very specific needs. The SIP library is also capable to automatically re-INVITE with changed codec set if the server or the peer device rejects the first INVITE due to codec incompatibility.

If you doesn't change the codec priorities with the parameters and you have enough CPU power and good network, than the default codec order will be the following (listed in priority order):

1. Opus wideband (enabled low priority 2)
2. speex wideband (enabled low priority 2)
3. G.729 (enabled low priority 2)
4. PCMU (enabled low priority 2)
5. PCMA (disabled 1)
6. speex ultrawideband (disabled 1)
7. opus ultrawideband (disabled 1)
8. opus narrowband (disabled 1)
9. speex narrowband (disabled 1)
10. GSM (disabled 1)
11. iLBC (disabled 0)

To prefer a codec you just have to set it's priority to 3 (use `_myfavoritecodec=3`).

This will automatically enable and put your selected codec as the highest priority one.

If you set all codec with the same priority, then the real priority will be the following:

1. Opus wideband
2. Speex wideband
3. G729
4. G711
5. Gsm
6. Opus narrowband
7. Speex narrowband
8. Ilbc (lowest priority)

Note:

- It is not guaranteed that the endpoints will consider the codec order but normally the other endpoint usually will pick up the first codec, or AJVoIP will pick-up the first in this list from the list of codec's sent by the other peer
- Not all codec is available in the Basic and Standard license (The Advanced and Gold license contains all codec)

## How to prefer one codec?

### Method A:

Just set the [prefcodec](#) parameter.

### Method B:

If you prefer to use the `use_xxx` parameters for the codec settings, then just set the desired codec priority to 3 and set the priority for all other codes to 2. In this case you preferred codec will be used whenever the other endpoint supports it and other codec's are used only if otherwise the call would fail.

For example the following parameters will set g.729 as the preferred codec and will enable also pcmu and gsm:

```
-use_g729=3
-use_pcmu=2
-use_pcma=1
-use_gsm=2
-use_speex=1
-use_speexwb=1
-use_speexuwb=1
```

```
-use_opus=1
-use_opuswb=1
-use_opuswb=1
-use_opuswb=1
-use_ilbc=1
```

## How to close a video call

Once a video call is terminated, you will also need to remove or hide your video display user interface element. You can follow this sequence:

1. hangup the call by calling `hangup()` function (and/or catch the disconnected state of the call from the STATUS notifications)
2. optional: wait 2 seconds if you need a CDR record about the video call
3. remove/unload webphone fragment from `FrameLayout` (resource ID of `FrameLayout` received in `VideoCall`)

Note: you might use `RemoveVideo` function to remove the video display, but the better way is to just hide/destroy your container.

Example code:

```
//disconnect the call
sipstackinstance.Hangup();

//if you need CDR, then execute the below code a bit later from a 2 second timer

// remove/destroy webphone fragment
FragmentTransaction ft = getSupportFragmentManager().beginTransaction();
ft.remove(finstance.getSupportFragmentManager().findFragmentById(fragmentResId)).commit();
```

## Disconnect reasons

The disconnect reasons are reported in the following format: `code text`. (So you have the text after a space)

Code:

- Is a SIP disconnect request or answer code including BYE, CANCEL or any SIP response code above 300.
- If no disconnect message were received or sent then the code is **-1**.

Text:

The text is one of the followings:

1. local disconnect reasons (listed below)
2. disconnect reason extracted from SIP Warning or Reason headers
3. response text extracted from the first line of SIP responses (textual representation of the response code)
4. textual representation of the disconnect code

The local disconnect reasons can be one of the followings (extra details might be appended and new disconnect texts might be added in the future):

- notaccepted
- User Hung Up
- bye received
- cancel received
- authentication failed
- endpoint destroy
- no response
- call setup timeout
- ring timeout
- media timeout
- endpoint timeout
- tunneling calltime limit
- call max timer expired
- max call time expired
- max speech time expired
- not acked connection expired
- disconnect on transfer
- transferalways
- transfer timeout
- transfer fail
- transfer done
- transfer terminated
- transfer (other)
- refer received
- cannot start media
- not encrypted
- srtp fail
- srtp init fail
- disc resend
- failed media
- forward
- forwardonbusy

- forwardnoanswer
- forwardalways
- rejectbusy
- rejectonphonebusy
- call rejected by peer
- rejected by the peer
- rejected
- autoreject
- autoignore
- ignored

## SIP SDK Android integration

You can easily integrate your app with any other external service, Android service. These as nothing to do with services offered by a SIP library thus it has to be handled by yourself, however further integration with SIP can be easily handled by the AJVoIP capabilities as described in this documentation.

For example you might add tight integration with your or third-party apps or services by [launching other activities](#), [handling links](#), [interacting](#) with other apps, consuming HTTP API's or [displaying web content](#) from your website in your app.

## Native phone integration

Native integrations means extending the native phone services with SIP capabilities by integrating your app with the Android OS.

For example you can easily implement native call integrations means handling calls made from the standard android dialer. With other words you can capture calls initiated by the native android dialer and handle it with your SIP application instead of the mobile service network.

We haven't added this functionalities inside the library since it requires user interface integration which is not suitable for a headless SDK, however we wrote a [Android Native SIP Call Integration](#) guide to help you with these tasks, covering the most important topics.

Beyond SIP call integration, this guide also covers some other topics such as managing the Android phone call history or acquiring the user phone number.

## Contact management

This FAQ point is to help you with managing contacts if that is required for your needs.

[Basic contact management API](#) is included also in AJVoIP for your convenience, however usually it is recommended to handle this in your app after your specific requirements as it is usually highly coupled with user interface thus not much to do with a headless SIP library.

Below we will present a few simple code examples for your convenience:

- Get contacts list
- Get one contact details
- Create a contact
- Open native contact editor
- Call history

For the below examples to work, you will need `READ_CONTACTS` and `WRITE_CONTACTS` permissions.

- Let's start by getting the contact list with the below code

```
// retrieving contact list (id and name)
// if "searchName" parameter is not an empty String, then it will search for the contacts which names contain the specified String
public void GetContactsList(String searchName)
{
    Cursor cur = null;
    ContentResolver cr = MyApplication.getAppContext().getContentResolver();
    String selection = ContactsContract.Contacts.HAS_PHONE_NUMBER + " = 1";

    if (searchName != null && searchName.length() > 0) { selection += " AND " + ContactsContract.Contacts.DISPLAY_NAME + " LIKE \"%\" + searchName + \"%\""; }
    String[] projection = new String[] { ContactsContract.Contacts._ID, ContactsContract.Contacts.DISPLAY_NAME };

    // query the Contacts database and return contacts in Ascending order by name
    cur = cr.query(
        ContactsContract.Contacts.CONTENT_URI,
        projection,
        selection,
        null,
        ContactsContract.Contacts.DISPLAY_NAME + " ASC");

    if (cur != null && cur.getCount() > 0)
    {
        // iterate through the cursor and get each contact ID and name
        while (cur.moveToNext())
        {
            if (cur.getString(cur.getColumnIndex(ContactsContract.Contacts._ID)) != null &&
```

```

cur.getString(cur.getColumnIndex(ContactsContract.Contacts.DISPLAY_NAME)) != null)
{
    // one single contact ID and name
    String contactId = cur.getString(cur.getColumnIndex(ContactsContract.Contacts._ID));
    String contactName = cur.getString(cur.getColumnIndex(ContactsContract.Contacts.DISPLAY_NAME));

}
}
}
if(cur != null){ cur.close(); cur = null; }
}

```

- b) Once we have the contact list, we can get any contact details by ID. In the following example we are querying just for the contact phone number, but any other field of interest can be queried the same way:

```

// get numbers and number types from a contact
public void GetContactPhoneNumbers(String contactId)
{
    ContentResolver cr = MyApplication.getAppContext().getContentResolver();
    Cursor cur = null;

    // get phone numbers and phone number types
    cur = cr.query(
        ContactsContract.CommonDataKinds.Phone.CONTENT_URI,
        null,
        ContactsContract.CommonDataKinds.Phone.CONTACT_ID + " = ?",
        new String[]{contactId}, null);

    int i = 0;
    if (cur != null && cur.getCount() > 0)
    {
        while (cur.moveToNext())
        {
            // a contact can have multiple phone numbers associated to it
            // for more details about phone number type, check the documentation here:
            https://developer.android.com/reference/android/provider/ContactsContract.CommonDataKinds.Phone
            String phoneNumber = cur.getString(cur.getColumnIndex(ContactsContract.CommonDataKinds.Phone.NUMBER));
            String numberType = cur.getString(cur.getColumnIndex(ContactsContract.CommonDataKinds.Phone.TYPE));
            String numberId = cur.getString(cur.getColumnIndex(ContactsContract.CommonDataKinds.Phone._ID));

        }
    }

    if(cur != null){ cur.close(); cur = null; }
}

```

- c) We can also create new contacts using the below code example:

```

public void CreateContact(String name, String phone)
{
    ContentResolver cr = getContentResolver();

    String accountType = null;
    String accountName = null;

    // create a raw contact and insert its name
    ContentValues values = new ContentValues();
    values.put(ContactsContract.RawContacts.ACCOUNT_TYPE, accountType);
    values.put(ContactsContract.RawContacts.ACCOUNT_NAME, accountName);

    Uri rawContactUri = cr.insert(ContactsContract.RawContacts.CONTENT_URI, values);
    long rawContactId = ContentUris.parseId(rawContactUri);

    values.clear();
    values.put(ContactsContract.Data.RAW_CONTACT_ID, rawContactId);
    values.put(ContactsContract.Data.MIMETYPE, ContactsContract.CommonDataKinds.StructuredName.CONTENT_ITEM_TYPE);
    values.put(ContactsContract.CommonDataKinds.StructuredName.DISPLAY_NAME, name);

    cr.insert(ContactsContract.Data.CONTENT_URI, values);

    // insert contact details (phone numbers and number types)
    Uri insertDetailsUri = Uri.withAppendedPath(rawContactUri, ContactsContract.Contacts.Data.CONTENT_DIRECTORY);
    values.clear();
    values.put(ContactsContract.Data.MIMETYPE, ContactsContract.CommonDataKinds.Phone.CONTENT_ITEM_TYPE);
    values.put(ContactsContract.CommonDataKinds.Phone.NUMBER, phone);
    values.put(PHONE_TYPE, ContactsContract.CommonDataKinds.Phone.TYPE_MOBILE);

    getContentResolver().insert(insertDetailsUri, values);
}

```

- d) Open native contact editor



```
Intent intent = new Intent(Intent.ACTION_EDIT);
Uri uri = Uri.withAppendedPath(ContactsContract.Contacts.CONTENT_URI, String.valueOf(contactId));
intent.setData(uri);
act.startActivity(intent);
```

#### e) Call history

An example code to manage the native call history can be found in this [guide](#).

## SIP SDK for Delphi

The AJVoIP SIP SDK can be also used from Delphi or C++ Builder, for example to build a softphone in Embarcadero FireMonkey. The AJVoIP library was created with API level suitable for Delphi, using support library for new features, thus it fulfills to Delphi requirements. You will need to [use the .jar](#) file included in the AJVoIP download (not the .aar file) and create a native bridge to it using the [Java2OP](#) tool.

Follow [this guide](#) to add the AJVoIP jar to your Delphi or C++Builder project.

You can [find](#) more examples and guides over the internet.

Once the AJVoIP.jar file is added to your project, have a look at the [quick start guide](#) first, then check the details from this documentation.

The sample project was created for Android Studio, but the logic is the same. The relevant details are in the [MainActivity.java](#) file. Just rewrite it with Delphi or C++ Builder syntax or implement a similar logic in Delphi / C++ Builder.

## New user registration / sign-up

You might need such functionality if you wish to implement a SIP softphone, however there is no such service provided by the standard SIP protocol thus each service is handling this functionality in a proprietary way. Usually the softswitch will expose a simple HTTP API (XML or JSON GET/POST/PUT) for this which you can call from your application. Contact your service provider or SIP server documentation for the details about such an API.

Another possibility would be to integrate your “Sign-Up” webpage into your app as a WebView.

## How to send SMS

Since this SIP library is intended to run mainly on SMS capable devices, usually there is no demand for built-in SMS functionality. However if you wish integrate SMS functionality into your application, we can recommend the following options:

### Use the platform native SMS capabilities

This can be achieved with a single line of code:

```
startActivity(new Intent(Intent.ACTION_VIEW, Uri.parse("sms:" + phonenumber)));
```

In case if you wish to preset the message text:

```
Intent intent = new Intent(Intent.ACTION_VIEW, Uri.parse("sms:" + phoneNumber));
intent.putExtra("sms_body", message);
startActivity(intent);
```

You can also send SMS without user interaction using the [android.telephony.SmsManager](#) capabilities.

In this case you will need to add the following permission: `<uses-permission android:name="android.permission.SEND_SMS"/>`

### Use your SIP server SMS capabilities

It might be possible that you wish to offer SMS capabilities for your endusers, especially if you can get offer better pricing than the mobile service provider.

In this case the SMS are sent usually with one of the following methods:

- Using your server API: some SIP servers expose a HTTP API (PUT/POST/GET with clear text, JSON, XML or other payload) which can be easily integrated with SIP client applications. Just perform the API call as specified in your server documentation.
- Using standard SIP IM: some SIP server is capable to convert regular SIP text messages ([RFC 3428](#)) to SMS when the target number is a routable mobile phone number.  
In this case you just need to use the [SendSMS](#) API. Optionally you might set the [haschat](#) parameter to 2 to signal to the SIP server that your intention is to send SMS.

## Handling incoming SMS

Special handling of incoming SMS messages doesn't have much meaning on an SMS capable devices since the OS is already capable to handle this task.

In case if your SIP server might send SMS over IP, then you have a few possibilities to handle it:

- Using the SIP protocol to handle SMS message ([RFC 3428](#)). In this case you don't need to do anything special as the messages are processed like regular IM extra. This should be the preferred delivery method of SMS messages in SIP networks.
- PUSH: you can use a server initiated push protocol for SMS delivery. The most effective is the usage of the cloud based [push notifications](#)
- Polling: this means requesting a server API from a timer to see if there is any new message arrived. Ineffective as it consumes extra CPU on both the server and client side thus it is not recommended especially in large networks, however due to its easy implementation this might be convenient in specific apps with a smaller user base if your SIP server (softswitch/PBX) doesn't support any other method
- Other protocols: you might handle incoming SMS with other proprietary or standard protocol like XMPP

## How to implement IM

IM (Instant message/chat) is well supported by AJVoIP. Make sure that your server has support for [SIP MESSAGE](#).

### Basic IM:

The core chat functionality can be implemented very easily:

- To send a text message just use the [SendChat](#) function. Example: `SendChat(-1, "john", "", "Hi!")`
- Incoming text messages can be cached by the [CHAT](#) notifications. Example: `"CHAT,1,john,Hi!"`

Usually you will have to maintain a separate thread with each peer (displaying the conversations on a separate page by peer).

### Optional features:

Once the simple chat send/receive is working, you might add some extra functionalities:

- Handle delivery success/failure:
  - You might parse the [CHATREPORT](#) notifications to notify the user if the message was delivered successfully or failed.
- Typing notifications:
  - You might use the `SendChatIsComposing` function to send typing notification to the peer.
  - Also parse the incoming [CHATCOMPOSING](#) messages (usually displaying something like "John is typing...").
- Group chat:
  - If you wish to implement group chat, then you should send/accept the group name which is usually the members separated by | . Example: `"emma | john | linda"`
  - When sending, use the group parameter of the `SendChat`. Example: `SendChat(-1, "emma", "emma | john | linda ", "Hi")`
  - For receiving, check if the message begins with the `"GROUP: xy:"` substring where xy is the group.
  - Usually you have to display each group as a separate thread (separate window for each group name). If group name doesn't exist, then use the peername.
- Offline messaging:
  - Offline messaging means queuing messages for later delivery when immediate delivery fails.
  - Offline messaging is automatically handled by AJVoIP unless you set the [offlinechat](#) parameter to 0.

Beyond the IM SIP protocol offered by AJVoIP, chat is mostly about user interface. Implement a nice GUI with handy features such as threaded messaging, send picture (using the file send API), emoticons and any other features for your users.

## How to implement PTT?

Push-to-talk or press-to-transmit (PTT) is an one-way communication method to mimic legacy half-duplex communication lines using a button to switch from voice reception mode to transmit mode. The feature is often used for door phones, walkie-talkies or industrial control functions.

PTT can be implemented by using the [Hold](#) function.

If somehow call hold is not well supported by your server or the remote peer, then you might use [Mute](#) instead.

*Other related functions and parameters which you might use are the followings:*

*IsMuted, IsOnHold, HoldChange, automute, autohold, holdtypeonhold, muteonhold, defmute, sendtrponmuted*

## Caller ID display

For outgoing calls the Caller ID (CLI)/A number display is controlled by the server and the application at the peer side (be it a VoIP softphone or a pstn/mobile phone). Caller-ID means the remote username, extension number or real phone number as sent by your SIP server. The SIP server might or might not forward the remote real caller-id or might replace it to any arbitrary value (such as the CLI number associated to the user, the user extension or auth id).

You can use the following parameters to influence the caller id display at the remote end:

-username  
-authusername/sipusername  
-displayname

Some VoIP server will suppress the CLI if you are calling to pstn and the number is not a valid DID number or AJVoIP account doesn't have a valid DID number assigned (You can buy DID numbers from various providers. This is up to your SIP server configuration and has nothing to do with AJVoIP).

The CLI is usually suppressed if you set the caller name to "Anonymous" (hide CLI).

For incoming calls the Java softphone will use the caller username, name or display name to display the Caller ID. (SIP From, Contact and Identity fields extracted from the incoming INVITE).

You can also use headers such as preferred-identity to control the Caller ID display.

The Caller-ID is received with the STATUS notifications or you can query it with the GetCallerID API. You can also use the GetIncomingDisplay API which can return some more details about the caller such as the display name.

Example (fields containing information about the caller name or number highlighted with bold):

```
INVITE sip:bob@biloxi.com SIP/2.0
Via: SIP/2.0/UDP pc33.atlanta.com;branch=z9hG4brn7wmmo4h
Max-Forwards: 35
To: Bob <sip:bob@biloxi.com>
From: Alice <sip:alice@atlanta.com>;tag=871822
Call-ID: a82c41f1b65
CSeq: 1 INVITE
Contact: <sip:alice@pc33.atlanta.com>
P-Asserted-Identity: "Cullen Alice" <sip:alice@atlanta.com>
P-Asserted-Identity: tel:+14095361002
Content-Type: application/sdp
Content-Length: 142

...sdp content...
```

You can learn more [here](#) and [here](#).

## How to implement IM

IM (Instant message/chat) is well supported by AJVoIP. Make sure that your server has support for [SIP MESSAGE](#).

### Basic IM:

The core chat functionality can be implemented very easily:

- To send a text message just use the [SendChat](#) function. Example: `API_SendChat(-1, "john", "", "Hi!")`
- Incoming text messages can be cached by the [CHAT](#) notifications. Example: "CHAT,1,john,Hi!"

Usually you will have to maintain a separate thread with each peer (displaying the conversations on a separate page by peer).

### Optional features:

Once the simple chat send/receive is working, you might add some extra functionalities:

- Handle delivery success/failure:
  - You might parse the [CHATREPORT](#) notifications to notify the user if the message was delivered successfully or failed.
- Typing notifications:
  - You might use the `SendChatIsComposing` function to send typing notification to the peer.
  - Also parse the incoming [CHATCOMPOSING](#) messages (usually displaying something like "John is typing...").
- Group chat:
  - If you wish to implement group chat, then you should send/accept the group name which is usually the members separated by | . Example: "emma | john | linda"
  - When sending, use the group parameter of the `API_SendChat`. Example: `API_SendChat(-1, "emma", "emma | john | linda", "Hi")`
  - For receiving, check if the message begins with the "GROUP: xy:" substring where xy is the group.
  - Usually you have to display each group as a separate thread (separate window for each group name). If group name doesn't exists, then use the peername.
- Offline messaging:

Offline messaging means queuing messages for later deliver when immediate delivery fails.  
Offline messaging is automatically handled by AJVoIP unless you set the [offlinechat](#) parameter to 0.

Beyond the IM SIP protocol offered by AJVoIP, chat is mostly about user interface. Implement a nice GUI with handy features such as threaded messaging, send picture (using the file send API), emoticons and any other features for your users.

## P2P

How to use AJVoIP for peer-to-peer calls?

Registering to a SIP server has various [advantages](#), but JVoIP can be used also for peer to peer calls without using any SIP server for example to make direct calls between two AJVoIP instances or between AJVoIP and any other SIP endpoint (such as a third-party softphone on your local LAN).

In this case just set the [register](#) parameter to 0 and set the [serveraddress](#) parameter to the peer SIP endpoint address (IP:port) or use full SIP URI to make calls such as `API_Call(-1, '1111@192.168.1.8:5678')`.

To make AJVoIP reachable for incoming calls, you should set a fix value for the [signalingport](#).

For example if your phone IP address is 192.168.1.8 and you have set the signalingport to 5678, then remote peers can reach your AJVoIP instance by calling to `sip:1111@192.168.1.8:5678`.

## How to USSD

IMS USSD ([Unstructured Supplementary Service Data](#)) messages are described in the [3GPP TS 24.390](#) standard.

This service provides the support for UE or network initiated MMI strings including single requests and dialogs.

It is commonly used to send quick feature codes to/from mobile networks used for various purposes such as balance request, callback, MMI supplementary services and other operations.

First of all, make sure to enable USSD by setting the `ims3gpp_ussd` parameter to 1 or the `ims3gpp` parameter to 2 as described [here](#).

Use the [SendUSSD](#) function to send USSD strings.

Received USSD strings can be cached by the [USSD notifications](#).

A simple USSD message exchange looks like this:

1. API function call: `API_SendUSSD(-1, "INVITE", "*135#");` //initiate USSD dialog (for example ask for available credit)
2. notification: `USSD,1,1,sent` //message successfully sent
3. notification: `USSD,1,2,Enter PIN code` //incoming USSD message (for example network asking for extra info)
4. API function call: `API_SendUSSD(1, "INFO", "1234");` //send USSD answer with INFO
5. notification: `USSD,1,1,sent` //message successfully sent
6. notification: `USSD,1,2,Your credit is 5 USD` //incoming USSD message (for example final answer received in BYE)
7. API function call: `API_Hangup(1);` //just for sure in case if somehow the call was not disconnected by the server

## How to DTMF

DTMF means Dual-tone multi-frequency signaling and it is commonly used to send touch tones to the server or the other peer. On phone user interface this is usually handled by handling key press or presenting a phone interface to the user who can press the digits to be sent.

Using the SIP protocol, there are multiple ways to send DTMF digits which can be set by the [dtmfmode](#) parameter.

If you are using the built-in user interface then you can send DTMF digits by pressing the number buttons during a call and if a dtmf digit is received, then you will see it displayed on the user interface notification area.

DTMF digits can be sent using the [Dtmf](#) API.

Feedback about the delivery can be obtained by watching for the [INFO](#) notifications (you will receive INFO,OK when the message was successfully sent or INFO,ERROR if failed).

On incoming DTMF you will receive a [DTMF](#) notification.

## Custom INFO messages

You can send and receive custom SIP INFO messages in the SIP signaling as described in [RFC 2976](#).

*Note: If you are looking to send or receive DTMF digits, then you should look at the [above FAQ point](#) instead.*

To send a custom INFO message, use the [Info](#) function.

Feedback about the delivery (if necessary) can be obtained by watching for the [INFO](#) notifications (you will receive INFO,OK when the message was successfully sent or INFO,ERROR if failed).

[INFO](#) notifications are also triggered for incoming SIP INFO messages (INFO,REC).

## Transfer API usage

*Call transfer is about transferring a connected call with SIP REFER.*

*If you are looking to forward a (not yet connected) incoming call then you should use the [Forward](#) function instead.*

The transfer mode can be set with the [transfertype](#) parameter and the calls can be transferred with the [Transfer](#) function.

The call transfer is handled with the SIP REFER method as described in [RFC 3515](#), [RFC 5589](#) and [RFC 6665](#).

With **unattended transfer** using transfertype 1 the transfer will be executed immediately once you call the [Transfer](#) function (blind transfer; only a SIP REFER is sent).

With **unattended transfer** using transfertype 6 and holdontransfer 1 or 2 the call might be put on hold before transfer and reloaded on transfer fail.

With **attended transfer** (transfertype 5) you can use the following call-flow, supposing that you are working at A side and wish to transfer B to C:

With unattended transfer the transfer will be executed immediately once you call the [Transfer](#) function.

With attended transfer (transfertype 5) you can use the following call-flow (supposing that you are working at A side and wish to transfer B to C):

1. A call B (outgoing) or B call to A (incoming)  
A speaking with B
2. Call [Transfer](#) (-1,C)  
The call between A and B will be put on hold by A  
A will call to C and connect (consultation call; if call fails, then the call between A and C will be un-hold automatically)  
A speaking with C
3. The actual call transfer will be initiated when A disconnect the call (Hangup)  
REFER message will be sent to B (which tells to B to call C. usually by automatically replacing the A-B call with A-C)
4. After transfer events:  
-If transfer fails (B can't call C) the call between A and B will be will be un-hold automatically (if server sends proper notifications)  
-If the transfer succeeds (B called C) the call between A and B will be will be disconnected automatically (if server sends proper notifications)  
-If the server doesn't support NOTIFY, then the call can be un-hold or disconnected from the API (Hold(-2,false), Hangup(-1))
5. B speaking with C at this point if the transfer was successful

There are a few optional parameters related to call transfer which you might set after your needs:

[transfertype](#), transfwitreplace, allowreplace, discontransfer, disconincomingrefer, transferdelay, checksubscriptionstate, subscribefortransfer, holdontransfer, calltransferalways

## Line parameter

For simple use-case the **line** parameter for the API functions almost always can be just set to **-1**.

More details:

The **line** parameter is part of most of the [API functions](#) and means the channel number.

With this parameter you can specify the session for which a function call to be applied (such as a specific call if there are multiple simultaneous calls).

The following values are defined:

- -2: all channels
- -1: the current channel set previously by SetLine API or by other functions. Usually this will mean the first channel (1)
- 0 : undefined (this should not be received/sent for endpoints in call, but might be used for other endpoints such as register endpoints)
- 1: first channel
- 2 : second channel
- etc (you can control the max number of the channels with the maxlines parameter which is set to 4 by default)

Most commonly, you will have to always pass -1 as the channel number. You will have to use other values only if you will present a GUI where the user can select different lines or if you have some special requirement to handle the lines explicitly.

Otherwise, AJVoIP can do this automatically allocating new channels when needed.

The **line** parameter is also part for most of the [notifications](#) to inform you which session triggered the notification.

See the "Multiple lines" FAQ point below if you wish to handle the lines explicitly.

## Multiple lines

Multi-line means the capability to handle more than one call at the same time (multiple channels).

Multi-lines are handled automatically by default and you can skip this description if you don't wish to explicitly manipulate the different lines (for example allowing the enduser to hold/forward/transfer or do any other action per line separately).

This can be managed by the line parameter of the API functions (most functions has a line parameter) and by checking the line parameter of the STATUS and other notifications (most notifications has a line number).

By default you don't need to do anything to have multi-line functionality as this is managed automatically with each new call on the first "free" line. This means that you just need to pass -1 as the line number with any function call and look only the notifications with the line number set to -1 (the global phone state).

If you wish to manage the lines explicitly, then you should pass the desired line numbers with the API calls and also look for the notifications received from the individual lines (such as the line parameter of the STATUS notification). This is necessary for example if you wish to create a user interface where the users can select/change to a specific line (line selector or line buttons).

### Multi-line vs multi-account

[Multiple accounts](#) refers to the feature when you might have more than one SIP account (on the same or separate SIP servers).

Multi-lines is described here and refers to the feature when you might need to handle multiple phone channels usually for multiple simultaneous calls or call transfer.

You can also have multi-accounts and multi-lines at the same time (multiple simultaneous calls via multiple accounts).

### Multi-line vs Conference

When we refer to "multi-line" we mean the capability to have multiple calls in progress at the same time. This doesn't necessarily means conference calls. You can initiate multiple calls by just using the [Call](#) API multiple times (to initiate calls to more than one user/phone), so you can talk with remote peers independently (all peers will hear you unless you use hold on some lines, but the peers will not hear each-others).

To turn multiple calls into a conference, you need to use the [Conf](#) API (or use the conference button from the [softphone.html](#)). When you have multiple peers in a conference, all peers can hear each-other.

### Usage

- Just set the line parameter to -1 for all/most function calls and parse only notifications with line -1 if you don't wish to deal with multiple lines explicitly. In this case AJVoIP will handle all the details and will guess which lines to use.
- However, if you have some special requirements to handle the lines/calls in a different way, then try to be strict with the line numbers: try to always pass the correct line parameter for the API calls and process the notifications from different lines according to your app requirements.

### Enable multi-line

There is nothing to be done to enable multi-line functionality as it is enabled and handled by default.

Optionally you might set the following parameters if your use-case requires multiple simultaneous calls:

- [aec](#): 0
- [aec2](#): 0
- [agc](#): 0
- [focusaudio](#): 1

### Disable multi-line

You can disable multi-line functionality with the following settings:

- set the "[multilinegui](#)" parameter to 0
- set the "[rejectonbusy](#)" setting to "true"

Other related parameters are the "[automute](#)" and "[autohold](#)" settings.

### Channel settings

Individual lines are initialized with the global parameters and their behavior might change depending on the circumstances and usage.

Some parameters can be also set line by line using the [SetLineParameter](#) function (avoid using this when possible and use the other API's instead to influence the behavior of specific individual lines).

### API

Most API functions has a line parameter which you can set to specify the line number. Some API's such as the [GetLineStatus](#) have been implemented to help you using multiple lines.

Also there are two specific API to set/get the current active line:

- [SetLine\(line\)](#); // Will set the current line. Just set it before other API calls and the next API calls will be applied for the selected line
- [GetLine\(\)](#); //Will return the current active line number. This should be the line which you have set previously except after incoming and outgoing calls (will automatically switch the active line to a new free line for these if the current active line is already occupied by a call)

The active line is also switched automatically on new outgoing or incoming calls (to the line where the new call is handled).

### Notifications

Check the line parameter for the [STATUS](#) and other [notifications](#) and update your line state machine accordingly and/or change your user interface accordingly.

## Channels

The following line numbers are defined:

- -3: in some functions you can refer to the next session with the line parameter set to -3
- -2: all (some API calls can be applied to all lines. For example calling hangup(-2) will disconnect all current calls)
- -1: current line (means the currently selected line or otherwise the “best” line to be used for the respective API)
- 0: undefined (this should not be received/sent for endpoints in call, but might be used for other endpoints such as register endpoints)
- 1: first channel
- 2: second channel
- ...
- N: channel number X

Note: If you use the **SetLine** with -2 and -1, it might be remembered only for a short time; after that the **GetLine** will report the real active line or “best” line.

API usage example:

```
Call(1, '1111'); //make a call on the first line
Call (2, '2222'); //make a second call on the second line

//setup conference call between all lines
Conf(); //interconnect current lines

//put first call on hold
Hold (1,true);

//disconnect the second call
Hangup(2, true);
```

## How to get the audio stream?

The Android VoIP SDK is capable to stream the received/sent media to a custom local port.

This is useful if you wish to make some processing on the audio streams such as speech to text or other analysis.

Just launch an UDP socket on any port and set this port number as the sendmediain\_to and/or sendmediaout\_to parameter for the SDK. Then you will receive the media streams from the calls being made.

Parameters:

**sendmedia\_type**

Specify the media stream format:

0: raw wave format (linear PCM) for narrowband (8 kHz 16 bit mono PCM files at 128 kbits - 15 kb/sec) or 16 kHz for wideband.

1: for RTP format (RTP header + payload with the actual media codec)

2: convert sample rate to raw PCM 8kHz (useful if original stream is in 16kHz format such as Opus or Speex wideband, but you need 8kHz PCM)

3: convert sample rate to raw PCM 16kHz (useful if original stream is in narrowband 8kHz format but you need 16kHz PCM)

4: RTP data only, without RTP header (raw codec format)

Default is 0.

*Note: It is recommended to set this to 0 or 1 and force a codec to match your needs (use OPUS or Speex if you need 16kHz PCM wideband or other codec if you need 8kHz PCM narrowband), however if you need raw audio in other sample rate then you might set it to 2 or 3 for sample rate conversion.*

**sendmediain\_to**

Specify your UDP port where you wish to receive remote audio (received from other peer for playback on local speaker)

Default is 0 which means no streaming.

**sendmediaout\_to**

Specify your UDP port where you wish to receive local audio (recorded from mic which is sent to the other end)

Default is 0 which means no streaming.

Notes:

*You might force G.711 codec for the AJVoIP to simplify the audio formats conversion (disable all codec's except PCMU and PCMA)*

*This is about streaming to your own or to a third-party application.*

*If you need to stream an audio file to a remote SIP endpoint, just use the [PlaySound](#).*

## Work with audio streams

If you have set audio streaming as it was discussed above, then you have the following possibilities to handle it:

### 1. Third party software:

Use some third-party software which is capable to playback raw PCM packets.

### 2. RTP stream:

If you have a software which is capable to process RTP packets then just set the sendmedia\_type to 1 so the AJVoIP will emit RTP packets which can be processed as is by such software.



### 3. PCM stream:

Use the default PCM stream if you don't have any ready to use software and you have to write it yourself. The packet emitted by the SIP media stack can be processed as-is by any audio player module.

### 4. Wave files:

If you don't need real-time audio, then just use the [voicerecording](#) and related parameters to obtain voice files in wave or other formats at the end of each call.

### 5. Barge-In:

If you just wish to listen into conversation, then you can use the AJVoIP itself for the job. Its barge-in feature allows you to bare into any call and create a hidden conference endpoint, so you can hear the conversation. This is often used in callcenters by supervisors. Contact our support if you need this module.

### 6. SIP media streaming:

Use the [PlaySound](#) function if you need to stream an audio file to a remote SIP endpoint.

## Native libraries

AJVoIP is implemented mostly in pure Java, however it also includes some native libraries for codec and audio processing. The SDK works fine even without these native libraries since all of them has Java fallback implemented.

The following ABI's are included by default, which will cover 99% of the devices with native audio and codec support:

- armeabi-v7a
- arm64-v8a

We found that this is the [optimal](#) set of libraries to be able to cover all platforms with minimal additional size.

The rest will fallback to java code (thus you will have 100% device coverage!)

A good estimation about the market can be learn from [here](#). See the CPU models chart at the bottom of the page.

- armeabi-v7a: this alone covers 98% of all devices on the market
- arm64-v8a: this is for the 64bit ARM architecture which is required by the Google Play
- x86: less then 1% of devices are using Intel x86 devices and they can use the java implementation
- mips: we include only fake support for mips so the Google Play will not exclude these kind of devices. MIPS market size is near 0% and on these kind of devices AJVoIP will just fallback to pure java code
- armeabi: not supported. This is a very old architecture so we haven't included armeabi libs due to size considerations as its market size is near 0% and also Android [removed ARmv5/ARmv6 support](#) since Android 4.4 (API level 19). We neither included a fake library because we found that if included then some devices might load the armeabi library even if they have support for armeabi-v7a
- x86\_64: there are no such devices on the market and it can fallback to java if required by some new devices released in the future
- mips64: there are no such devices on the market and anyway it is covered with the fake mips support with Java fallback

If somehow you wish to change the included native libraries, you can download the whole set from [here](#). For example you might include the armeabi libs if your app uses some [other](#) native library and you wish to provide support for these ancient devices for some reason.

## Dependencies

AJVoIP uses one or more of the following Android libraries, depending on your build (listing here in case if somehow you encounter some incompatibility issues due to other versions used by your app):

- android.jar (compiled with android 23 sdk)
- multidex-1.0.2.aar (classes.jar, to split the output)
- androidx.legacy:legacy-support-v4:1.0.0
- firebase-messaging-10.0.1.aar (in classes.jar, might be required for push notifications)
- firebase-core-10.0.1.aar (in classes.jar, might be required for push notifications)
- firebase-analytics-10.0.1.aar (in classes.jar, might be required for push notifications)
- firebase-analytics-impl-10.0.1.aar (in classes.jar, might be required for push notifications)
- firebase-iid-10.0.1.aar (in classes.jar, might be required for push notifications)
- firebase-common-10.0.1.aar (in classes.jar, might be required for push notifications)
- play-services-tasks-10.0.1.aar (classes.jar)
- play-services-basement-10.0.1.aar (classes.jar)
- support-v4-24.0.0.aar (in classes.jar, might be required for forward compatibility)
- support-v4-24.0.0.aar (in internal\_impl-24.0.0.jar, might be required for forward compatibility)
- support-annotations-24.0.0.jar (might be required for forward compatibility)
- org.apache.http.legacy.jar (might be required for backward compatibility)

## How to work with logs?



Set the [loglevel](#) parameter to 5 and then the logs will appear on the Logcat (or can be polled with the GetLogs() function call).

You might look at the followings in the logs:

- Search for “catch”, “ERROR” and “WARNING” messages to find any issues. Please note that logs generated with loglevel 3 or higher will often includes lot’s of not so important “WARNING” messages which can be safely ignored
- Check for the SIP signaling. You can find out register or call issues by just following the SIP signaling logs. (Find out the suspicious message then search for it’s Call-ID value across the log to walk through the messages which belongs to the same session)
- Search for “call details” to get a high level overview about your calls(s). A “call details” statistics is generated after each call.
- Other log messages might be too specific or technical but you might still be able to have a gasp about the cause of the problems by looking at the logs

## ERROR and WARNING messages in the log

If you set AJVoIP loglevel higher than 1 than you will receive messages that are useful only for debug. A lot of ERROR and WARNING message cannot be considered as a fault. Some of them will appear also under normal circumstances and you should not take special attention for these messages. If there are any issue affecting the normal usage, please send the detailed [logs](#) to Mizutech support ([info@mizu-voip.com](mailto:info@mizu-voip.com)) in a text file attachment.

Some internal exceptions (such as “java.lang.NumberFormatException”) are normal in some circumstances and can be safely ignored.

### RTP warning in my server log

AJVoIP will send a few (maximum 10) short UDP packets (\r\n) to open the media path (also the NAT if any).

For this reason you might see the following or similar Asterisk log entries:

```
WARNING[8860]: res_rtp_asterisk.c:2019 ast_rtp_read: RTP Read too short
Unknown RTP Version 1
```

These packets are simply dropped by Asterisk which is the expected behavior. This is not a AJVoIP or Asterisk error and will not have any negative impact for the calls. You can safely skip this issue.

You might turn this off by the “natopenpackets” parameter (set to 0). You might also set the “keepaliveival” to 0 and modify the “keepaliveival” (all these might have an impact on AJVoIP NAT traversal capability)

### Recording errors

You might see the following errors if AJVoIP doesn’t have permission for the audio device:

```
E/AudioRecord: AudioFlinger could not create record track, status: -1
E/AudioRecord-JNI: Error creating AudioRecord instance: initialization check failed with status -1.
E/android.media.AudioRecord: Error code -20 when initializing native AudioRecord object.
WARNING,recorder state is 0
```

Solution: make sure that the app has RECORD\_AUDIO [permissions](#).

### Method exceeds compiler instruction limit

You should enable multidex as described [here](#):

```
dependencies {
    implementation 'com.android.support:multidex:1.0.3'
}
```

## How to send logs?

If you have any problem with the Android SIP library, Mizutech support most probably will ask you to send a problem description (your question, bug report or any integration issue) and logs about the problem.

For this the [loglevel](#) parameter must be set to 5 and then the logs will appear on the [logcat](#) (or can be polled with the GetLogs() function call or logs written to file).

Once you reproduced the problem, send the content of the logs to [info@mizu-voip.com](mailto:info@mizu-voip.com) as email text file attachment and an exact description of the problem (also include instructions for reproductions if possible).

Make sure that the log contains also the AJVoIP startup (send the logs from the very beginning, not only the part when the problem might appear).

If the problem is call related, then make sure to have only one call in the log. That one in which the problem was reproduced.

In addition to the log file, Mizutech support might ask one or two SIP account valid on your server to be able to reproduce the problem.

*In case if AJVoIP is integrated into your app, make sure that your app has some debug functionality, capable to collect and save/export/send AJVoIP logs.*

## Resources

[Android VoIP SDK home-page](#)

[Android VoIP SDK Download](#)

[Sample project](#)

[Quick Start Guide](#)

[Documentation \(PDF\)](#)

[Documentation \(HTML\)](#)

[Documentation \(WinHelp\)](#)

[Javadoc \(download\)](#)

[Javadoc \(online\)](#)

[Native integration](#)

For help, contact [info@mizu-voip.com](mailto:info@mizu-voip.com)

*Copyright © Mizutech SRL*